

AOS/TOS STANDARD OPERATING PROCEDURE: DSLR Configuration

| PREPARED BY | ORGANIZATION | DATE |
|----------------|--------------|------------|
| Courtney Meier | FSU | 12/04/2015 |
| Oliver Smith | FSU | 12/04/2015 |

| APPROVALS | ORGANIZATION | APPROVAL DATE |
|-------------------|--------------|---------------|
| Andrea Thorpe | PROJ SCI | 1/27/2016 |
| Vladimir Aleksiev | PSE | 1/12/2016 |
| | | |
| | | |

| RELEASED BY | ORGANIZATION | RELEASE DATE |
|--------------|--------------|--------------|
| Anne Balsley | СМ | 1/27/2016 |

See configuration management system for approval history.

© 2016 NEON Inc. All rights reserved.

The National Ecological Observatory Network is a project solely funded by the National Science Foundation and managed under cooperative agreement by NEON, Inc. Any opinions, findings, and conclusions or recommendations expressed in this material are those of the author(s) and do not necessarily reflect the views of the National Science Foundation.



Change Record

| REVISION | DATE | ECO # | DESCRIPTION OF CHANGE |
|----------|-----------|-----------|--|
| A | 1/27/2016 | ECO-03528 | Initial release: Content for the Nikon D800/D810 previously contained in Leaf Area Index protocol moved to this document. New content developed and added for Nikon D750. |
| | | | |
| | | | |



TABLE OF CONTENTS

| 1 | DE | SCRIP | TION1 |
|---|---|---|-------------------------|
| | 1.1 | Purp | ose1 |
| | 1.2 | Scop | e1 |
| | 1.3 | Appli | ies To1 |
| | 1.4 | Ackn | owledgments1 |
| 2 | REI | LATED | DOCUMENTS AND ACRONYMS1 |
| | 2.1 | Appli | icable Documents1 |
| | 2.2 | Refe | rence Documents2 |
| | 2.3 | Acro | nyms2 |
| | 2.4 | Defir | nitions2 |
| 3 | SAI | FETY | 2 |
| | | | |
| 4 | PE | RSON | NEL AND EQUIPMENT |
| 4 | PE | | NEL AND EQUIPMENT |
| 4 | | Equip | |
| 4 | 4.1 | Equiț Train | pment3 |
| 4 | 4.1 4.2 4.3 | Equip Train Spec | pment |
| - | 4.1 4.2 4.3 | Equip Train Spec ANDAI | pment |
| - | 4.1 4.2 4.3 5.1 | Equip Train Spec ANDAI Conf | pment |
| - | 4.1 4.2 4.3 5.1 5.1 | Equip Train Spec ANDAI Conf 1.1 S | pment |
| - | 4.1 4.2 4.3 5.1 5.1 | Equip Train Spec ANDAP Conf 1.1 S 1.2 S | pment |
| - | 4.1 4.2 4.3 5.1 5.2 | Equip Train Spec ANDAI Conf 1.1 S 1.2 S Conf | pment |



LIST OF TABLES AND FIGURES

No table of figures entries found.

In your document, select the words to include in the table of contents, and then on the Home tab, under Styles, click a heading style. Repeat for each heading that you want to include, and then insert the table of contents in your document. To manually create a table of contents, on the Document Elements tab, under Table of Contents, point to a style and then click the down arrow button. Click one of the styles under Manual Table of Contents, and then type the entries manually.



1 DESCRIPTION

The Nikon DSLR must be configured appropriately in order to take satisfactory images for LAI analysis with the CanEye software. Configuration steps are broken down into two main sections below: 1) Settings adjusted prior to field work; and 2) Settings adjusted in the field. Both of these sections contains instructions grouped together by camera model. This document contains instructions for the cameras listed below:

- Nikon D750
- Nikon D800 / D810

1.1 Purpose

1.2 Scope

This document provides a change-controlled version of an Observatory procedure. Documentation of content changes (i.e. changes in particular tasks or safety practices) will occur via this change-controlled document, not through field manuals or training materials.

1.3 Applies To

The procedure described in this document is used in the following protocols:

| Doc # | Title |
|-----------------|--|
| NEON.DOC.014039 | TOS Protocol and Procedure: Measurement of Leaf Area Index |
| | |

1.4 Acknowledgments

2 RELATED DOCUMENTS AND ACRONYMS

2.1 Applicable Documents

Applicable documents contain higher-level information that is implemented in the current document. Examples include designs, plans, or standards.

| AD[01] | NEON.DOC.004300 | EHS Safety Policy and Program Manual |
|--------|-----------------|--|
| AD[02] | NEON.DOC.004316 | Operations Field Safety and Security Plan |
| AD[03] | NEON.DOC.001155 | NEON Training Plan |
| AD[04] | NEON.DOC.050005 | Field Operations Job Instruction Training Plan |

 $\ensuremath{\textcircled{}}$ 2016 NEON Inc. All rights reserved.



2.2 Reference Documents

Reference documents contain information that supports or complements the current document. Examples include related protocols, datasheets, or general-information references.

| RD[01] | NEON.DOC.000008 | NEON Acronym List |
|--------|-----------------|---------------------------------------|
| RD[02] | NEON.DOC.000243 | NEON Glossary of Terms |
| RD[03] | NEON.DOC.005003 | NEON Scientific Data Products Catalog |
| | | |

2.3 Acronyms

| Acronym | Definition |
|---------|-------------------------------------|
| DSLR | Digital Single Lens Reflex [camera] |
| LAI | Leaf Area Index |

2.4 Definitions

3 SAFETY

This document identifies procedure-specific safety hazards and associated safety requirements. It does not describe general safety practices or site-specific safety practices.

Personnel working at a NEON site must be compliant with safe field work practices as outlined in the Operations Field Safety and Security Plan (AD[02]) and EHS Safety Policy and Program Manual (AD[01]). Additional safety issues associated with this field procedure are outlined below. The Field Operations Manager and the Lead Field Technician have primary authority to stop work activities based on unsafe field conditions; however, all employees have the responsibility and right to stop their work in unsafe conditions.



4 PERSONNEL AND EQUIPMENT

4.1 Equipment

Table 1. Equipment needed to implement the procedures in this document.

| ltem No. | R/S | Description | Purpose | Quantity* | Special Handling | |
|----------|---------------|------------------|--------------------|-----------|---------------------|--|
| | Durable Items | | | | | |
| MX104649 | R | DSLR camera body | Capture DHP images | 1 | Ν | |
| MX104651 | R | Fisheye lens | Capture DHP images | 1 | Ν | |



4.2 Training Requirements

All technicians must complete required safety training as defined in the NEON Training Plan (AD[04]). Additionally, technicians must complete procedure-specific training for safety and implementation of this procedure as required in Field Operations Job Instruction Training Plan (AD[05]).

4.3 Specialized Skills

Familiarity with Nikon DSLR cameras.



5 STANDARD OPERATING PROCEDURES

The DSLR cameras must be configured appropriately, and used in accordance with very specific settings in order to take satisfactory hemispherical photos for LAI analysis with the image analysis software.

5.1 Configuring the Nikon D800/D810

5.1.1 Settings Adjusted Prior to Field Work

There are several suites of settings that need to be adjusted prior to shooting, and these can be grouped into a few general categories:

- Settings adjusted with physical buttons and knobs
- Settings adjusted with the camera software (playback, shooting, custom setting, and setup menus).
- A customizable menu called "My menu" can also be modified so that frequently adjusted settings are readily available.

Settings Adjusted with Physical Buttons and Knobs

Shutter-release mode

Desired setting = S (single shot). To adjust, press the button near the left control knob (below left), and rotate the outer-ring of the control knob until "S" is selected (below right).



Figure 1. Nikon D800/D810: Setting the shutter-release mode.



| Title: AOS/TOS Standard Operating Procedure: DSLR Configuration | | Date: 1/27/2016 |
|---|------------------------|-----------------|
| NEON Doc. #: NEON.DOC.001718 | Author: Courtney Meier | Revision: A |

Image quality

Desired setting = RAW. To adjust, press the "QUAL" button on the left control knob (below left), and rotate the primary wheel until "RAW" is displayed in the top LCD (below right).



Figure 2. Nikon D800/D810: Setting image quality to RAW.

White balance

Desired setting = Auto. To adjust, press the "WB" button on the left control knob (below left), and rotate the primary wheel until "WB A" is displayed in the top LCD (below right).



Figure 3. Nikon D800/D810: Adjusting white balance settings.

Bracketing

Desired setting = OFF. To adjust, press the "BKT" button (located in different places on the D800 vs. the D810), and rotate the appropriate wheel until BKT disappears from the LCD on the top of the body.



Metering mode

Desired setting = Matrix Metering. To adjust, rotate the outer ring of the "AE-L/AF-L" button to the center position (see below).



Figure 4. Nikon D800/D810: Setting the metering mode.

Settings Adjusted with Software Menus

Playback Menu: display options

Desired settings = show "Overview". With this option enabled, it is possible to evaluate the histogram of each image after it is acquired. To adjust,

 Press the "Menu" button, then use the "Multi-selector" button (circled below-right) to navigate to "Playback Menu → Playback display options".



Figure 5. Nikon D800/D810: Playback Menu display options.

2. Use the Multi-Selector to check the box next to "Overview".



- 3. Navigate to "Done" and press the "OK" button (the latter is located in the lower left of the image above).
- 4. To view histogram information for an image, press the "Play" button (circled in red below).



Figure 6. Nikon D800/D810: Location of the "Play" button.

- 5. Use the L and R arrow keys on the Multi-Selector to select the desired image.
- 6. Press the Up and Down arrow keys on the Multi-Selector to bring up the "Overview" histogram information (below). The red circle indicates the file name.



Figure 7. Nikon D800/D810: Locating the file name in the "overview" histogram view during file playback.



Shooting Menu: File naming

Desired setting = DXX, where XX = the unique NEON Domain number. To adjust, press the "Menu" button, and select "Shooting Menu \rightarrow File naming". Enter the appropriate alpha-numeric characters. When finished, "DSC" should no longer be displayed, and your custom characters should be.



Figure 8. Nikon D800/D810: Shooting Menu file naming options.

Shooting Menu: Color space

Desired setting = sRGB. To adjust, press "Menu", and select "Shooting Menu \rightarrow Color space". Select "sRGB" and press the "OK" button.



Figure 9. Nikon D800/D810: Shooting Menu color space options.



| Title: AOS/TOS Standard Operating Procedure: DSLR Configuration | | Date: 1/27/2016 |
|---|------------------------|-----------------|
| NEON Doc. #: NEON.DOC.001718 | Author: Courtney Meier | Revision: A |

Shooting Menu: Active D-lighting

Desired setting = AUTO. To adjust, press "Menu", and select "Shooting Menu \rightarrow Active D-Lighting". Select "Auto" and press the "OK" button.

| | SHOOTING MENU | |
|---|------------------------|--------|
| | NEF (RAW) recording | Ē, |
| - | White balance | AUTO |
| v | Set Picture Control | ENI |
| | Manage Picture Control | |
| | Color space | SRGB |
| 尼 | Active D-Lighting | E AUTO |
| | Vignette control | |
| ? | Long exp. NR | OFF . |

Figure 10. Nikon D800/D810: Shooting Menu Active D-lighting options.

Shooting Menu: High ISO noise reduction (NR)

Desired setting = Normal. To adjust, press "Menu" and select "Shooting Menu \rightarrow High ISO NR". Select "Normal" and press the "OK" button.







| Title: AOS/TOS Standard Operating R | Date: 1/27/2016 | |
|--------------------------------------|------------------------|-------------|
| <i>NEON Doc. #</i> : NEON.DOC.001718 | Author: Courtney Meier | Revision: A |

Shooting Menu: ISO sensitivity settings

Desired setting: Minimum shutter speed = 1/30; Maximum sensitivity = Hi2. To adjust, use the "Multi-Selector" and press the "OK" button on the desired settings.



Figure 12. Nikon D800/D810: Shooting Menu ISO sensitivity settings menu.

Custom Settings Menu: Autofocus

- Option "a2" (AF-S priority selection):
 - Option "a2" must be set to "Focus" in order for a 'beep' to be heard when the camera achieves focus lock when autofocus is turned on.

Custom Settings Menu: Metering/exposure

- Option "b1" (ISO sensitivity step value):
 - Set to a value of "1/3". This allows finer control over exposure via ISO settings.
- Option "b2" (EV steps for exposure cntrl):
 - Set to a value of "1/3". This allows finer control over exposure via changes to shutter speed and aperture.



Setup Menu: Time zone and date

The following settings must be adjusted:

- Time Zone
- Local time and date
- Date format = Y/M/D
- Daylight savings time i.e. ON/OFF depending on time of year



Figure 13. Nikon D800/D810: Setup Menu options for timezone and date.

Setup Menu: Image auto- rotation

Desired setting: Auto-Rotation = OFF. Required in order to force all captured images to Landscape orientation for compatibility with CanEye analysis. To adjust, use the multi-selector to navigate to "SETUP MENU \rightarrow Auto image rotation \rightarrow OFF" and press the "OK" button.



My Menu: Customizing "My Menu"

Any settings for which quick access is desired can be added to the customizable "My Menu" screen (image below). To add a setting to "My Menu",

- 1. Press "Menu", then select "My Menu \rightarrow Add items" (image below).
- 2. Scroll through the available settings menus until you find the setting you want to add to "My Menu".
- 3. With the setting highlighted, press the "OK" button.
- 4. Press "OK" again. The "My Menu" screen should now be modified.



Figure 14. Nikon D800/D810: My Menu customization.



5.1.2 Settings Adjusted in the Field

Exposure mode

To adjust, press the Mode button, and rotate the primary wheel until the top LCD shows the desired mode (A or M, depending on camera orientation that will be used).



Figure 15. Nikon D800/D810: Setting the desired Exposure mode.

Auto focus mode (downward-facing photos)

Desired setting = AF-S Auto. To adjust,

- 1. Move focus switch to "AF", then press and hold the button in the middle of the switch (below left).
- 2. Spin the primary and secondary wheels so the top LCD reads "AF-S" with "auto" above (below right).



Figure 16. Nikon D800/D810: Configuring focus mode to auto-focus for downward-facing photos.



Manual focus mode (upward-facing photos)

Desired setting = Manual. To adjust, set the focus switch to "M" (below left), and rotate the focus ring on the lens to " ∞ " (below right).



Figure 17. Nikon D800/D810: Configuring focus mode to manual for upward-facing photos.

ISO (sensor light sensitivity)

- Downward-facing DHPs: Desired setting = "ISO-auto", initial ISO = 400. To adjust, press the "ISO" button on the left control knob (below left), then rotate the secondary wheel until "ISO-auto" is displayed (below right). Then, still pressing the "ISO" button, rotate the primary wheel until ISO = 400 is displayed in the top LCD.
- Upward-facing DHPs: Desired setting = "ISO" (manual), initial ISO = 6400. To adjust, press the "ISO" button on the left control knob (below left), and rotate the secondary wheel until "ISO" is displayed (not "ISO-auto"). Then, still pressing the "ISO button, rotate the primary wheel until ISO = 6400 is displayed in the top LCD.



Figure 18. Nikon D800/D810: Configuring ISO settings for downward- and upward-facing photos.



Manually adjusting exposure with the Exposure Control meter

- 1. Look through the viewfinder to ensure the camera is metering the exposure for the scene you wish to capture.
- 2. Use the 'Primary wheel' to adjust the shutter-speed, and the 'Secondary wheel' to adjust the aperture until the image is properly exposed.
 - a. As you adjust the Primary and Secondary wheels, you will notice the Exposure Control meter at the bottom of the viewfinder moving left and right (see below, red circle).
 - b. The image is properly exposed when the exposure control indicator is centered.



Nikon D810 Viewfinder

Figure 19. The Nikon D800/D810 viewfinder; the exposure control meter is circled in red.



5.2 Configuring the Nikon D750

The Nikon D750 must be configured appropriately in order to take satisfactory images for LAI analysis with the CanEye software.

5.2.1 Settings Adjusted Prior to Field Work

There are several suites of settings that need to be adjusted prior to shooting, and these can be grouped into a few general categories:

- Settings adjusted with physical buttons and knobs
- Settings adjusted with the camera software (playback, shooting, custom setting, and setup menus).
 - The camera software on the D750 is largely identical to that of the D800/D810.
 - Reference software instructions in Section 5.1.1 above for software configuration steps.
- A customizable menu called "My menu" can also be modified so that frequently adjusted settings are readily available.

Settings Adjusted with Physical Buttons and Knobs

Shutter-release mode

Desired setting = S (single shot). To adjust, press the button near the left control knob (left red circle), and rotate the outer-ring of the control knob until "S" is selected (right red circle).



Figure 20. Nikon D750: Setting the shutter-release mode.



Image quality

Desired setting = RAW. To set the image quality to RAW, press and hold the QUAL button (circled below), and rotate the primary wheel (circled upper right on camera) until RAW is displayed on the rear LCD.



Figure 21. Nikon D750: Configuring image quality settings.

White balance

Desired setting = AUTO. To adjust, press and hold the "WB" button on the back of camera (below), and rotate the primary wheel until the AUTO setting is displayed on the large LCD.



Figure 22. Nikon D750: Configuring white balance settings.



Bracketing

Desired setting = OFF. To adjust, press and hold the 'BKT' button (circled below). The rear LCD will show "OF" toward the top-center. Rotate the primary wheel until 'number of shots' = 0; the letters 'BKT' should be absent from the top LCD.



Figure 23. Nikon D750: Toggling bracketing on and off.

Metering mode

Desired setting = Matrix Metering. To adjust, press metering button (circled below) until matrix metering symbol is displayed on LCD screen (same square symbol as on button).



Figure 24. Nikon D750: Configuring the metering mode.



Settings Adjusted with Software Menus

- The camera software on the D750 is largely identical to that of the D800/D810.
- Reference software instructions in Section 5.1.1 above for software configuration steps that are required prior to field work.

5.2.2 Settings Adjusted in the Field

Exposure mode

To adjust, press the button on the left / top control wheel, and rotate the wheel until the top LCD shows the desired mode (A or M, depending on camera orientation that will be used).

Auto focus mode (downward-facing photos)

Desired setting = AF-S Auto. To adjust,

- 1. Move focus switch on lower front left of camera to "AF" (Figure 26), then press and hold the button in the middle of the switch.
- 2. Spin the primary and secondary wheels so the top LCD reads "AF-S" with "Aut" on the right (below).



Figure 25. Nikon D750: Top LCD display when camera is configured for single-servo auto-focus auto-mode, where the camera software automatically determines which of the 51 available focus points are used to focus the lens on the subject.



Manual focus mode (upward-facing photos)

Desired setting = Manual. To adjust, set the focus switch to "M" (below left), and rotate the focus ring on the lens to " ∞ " (below right).



Figure 26. Nikon D750: Focus mode switch, with auto-focus selector button in middle of switch.

ISO (sensor light sensitivity)

- Downward-facing DHPs: Desired setting = "ISO-auto", initial ISO = 400. To adjust, press the "ISO" button (below left), then rotate the secondary wheel until "ISO-auto" is displayed. Then, still pressing the "ISO" button, rotate the primary wheel until ISO = 400 is displayed in the top LCD.
- Upward-facing DHPs: Desired setting = "ISO" (manual), initial ISO = 6400. To adjust, press the "ISO" button (below left), and rotate the secondary wheel (on front) until "ISO" is displayed (not "ISO-auto"). Then, still pressing the "ISO button, rotate the primary wheel until ISO = 6400 is displayed in the top LCD.



Figure 27. Nikon D750: Configuring ISO sensitivity settings.



Manually adjusting exposure with the Exposure Control meter

- 1. Look through the viewfinder to ensure the camera is metering the exposure for the scene you wish to capture.
- 2. Use the 'Primary wheel' to adjust the shutter-speed, and the 'Secondary wheel' to adjust the aperture until the image is properly exposed.
 - a. As you adjust the Primary and Secondary wheels, you will notice the Exposure Control meter at the bottom of the viewfinder moving left and right (see below, red circle).
 - b. The image is properly exposed when the exposure control indicator is centered.



Nikon D750 Viewfinder

Figure 28. The Nikon D750 viewfinder; the exposure control meter is circled in red.



5.3 Lenses

5.3.1 Nikkor 16 mm Fisheye f/2.8

Fisheye lens f-stop ring

Newer models of the Nikkor 16mm Fisheye lens may have a manually-adjustable f/stop ring, and a switch that toggles manual lens control versus control through the D800 body. We wish to maintain control of f/stops through the DSLR body. To do this:

- 1. Rotate the f/stop ring on the lens to f/22 (the "f22" text printed on the lens should be red).
- 2. Toggle the lens switch to the red dot. This will prevent further manual movement of the lens f/stop ring, and allow changes to f/stops to only occur via the camera.