

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

AOS PROTOCOL AND PROCEDURE: AQUATIC MACROINVERTEBRATE SAMPLING

PREPARED BY	ORGANIZATION	DATE
Stephanie Parker	AQU	12/01/2017

APPROVALS	ORGANIZATION	APPROVAL DATE
Dave Tazik	SCI	1/16/2018
Mike Stewart	PSE	1/15/2018

RELEASED BY	ORGANIZATION	RELEASE DATE
Anne Balsley	CM	01/19/2018

See configuration management system for approval history.

The National Ecological Observatory Network is a project solely funded by the National Science Foundation and managed under cooperative agreement by Battelle. Any opinions, findings, and conclusions or recommendations expressed in this material are those of the author(s) and do not necessarily reflect the views of the National Science Foundation.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

Change Record

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
A	01/22/2016	ECO-03470	Initial release, supersedes NEON.DOC.000690 and NEON.DOC.001204.
B	02/08/2017	ECO-04359	Update NEON template; Separate and rename snag sampling SOPs; Update sample ID template; Add DNA metabarcode SOP
C	01/19/2018	ECO-003046	Tape jar lids for shipping, remove mini surber, move datasheets to appendix

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

TABLE OF CONTENTS

1 OVERVIEW 1

1.1 Background 1

1.2 Scope..... 2

1.2.1 NEON Science Requirements and Data Products 2

1.3 Acknowledgments..... 2

2 RELATED DOCUMENTS AND ACRONYMS 3

2.1 Applicable Documents 3

2.2 Reference Documents..... 3

2.3 Acronyms 4

2.4 Definitions..... 4

3 METHOD 10

4 SAMPLING SCHEDULE 13

4.1 Sampling Frequency and Timing 13

4.2 Criteria for Determining Onset and Cessation of Sampling..... 13

4.3 Timing for Laboratory Processing and Analysis 13

4.4 Sample Timing Contingencies 13

4.5 Criteria for Permanent Reallocation of Sampling Within a Site..... 15

4.6 Sampling Specific Concerns 16

4.7 Safety 17

5 PERSONNEL AND EQUIPMENT..... 18

5.1 Equipment..... 18

5.2 Training Requirements..... 29

5.3 Specialized Skills..... 29

5.4 Estimated Time 29

6 STANDARD OPERATING PROCEDURES 30

SOP A PREPARING FOR SAMPLING 30

SOP B DETERMINING SAMPLING LOCATIONS AND SAMPLER TYPE..... 32

SOP C FIELD SAMPLING 35

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

SOP D MACROINVERTEBRATE DNA METABARCODE FIELD COLLECTION.....58

SOP E LABORATORY SAMPLING AND ANALYSIS59

SOP F DATA ENTRY AND VERIFICATION60

SOP G SAMPLE SHIPMENT61

7 REFERENCES63

APPENDIX A DATASHEETS65

APPENDIX B QUICK REFERENCES66

APPENDIX C REMINDERS68

APPENDIX D ESTIMATED DATES FOR ONSET AND CESSATION OF SAMPLING69

APPENDIX E SITE-SPECIFIC INFORMATION: HABITAT AND SAMPLER RECOMMENDATIONS70

APPENDIX F PAPER DATASHEET EXAMPLES.....71

LIST OF TABLES AND FIGURES

Table 1. Contingent decisions..... 14

Table 2. Contingent decisions for sampling in a wadeable stream. 16

Table 3. Equipment list – General equipment..... 18

Table 4. Equipment list – Macroinvertebrate Samplers..... 21

Table 5. Equipment list – Macroinvertebrate field elutriation and preservation 24

Table 6. Equipment list – Laboratory processing: preservative replenishment..... 25

Table 7. Equipment list – Shipping supplies 28

Table 8. Examples of sample IDs generated by the mobile app..... 31

Table 9. Datasheets associated with this protocol..... 65

Figure 1. Mayflies (Ephemeroptera: Heptageniidae) are scrapers that are adapted to feed most efficiently on attached periphyton in flowing waters..... 1

Figure 2. Caddisflies (Trichoptera) often build cases out of small pebbles, sand, or pieces of small woody debris. 5

Figure 3. Black fly (Diptera: Simuliidae) larva, an invertebrate that uses fanlike mouthparts to strain particulates from moving water. 5

Figure 4. Freshwater mussels are often found in streams. Pictured here, lampmussels (*Lampsilis virescens*) from Alabama..... 7

Figure 5. A mayfly predator feeding on another aquatic invertebrate. 7

Figure 6. Mayfly scrapers feeding on a rock surface. 8

Figure 7. A stonefly shredder feeding on plant detritus in a stream..... 8

Figure 8. *Elimia* is a genus of snail often found in rivers and streams. 9

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Figure 9. Step pools occur in high-gradient streams where there are channel-spanning pools separated by boulder/cobble steps. 9

Figure 10. Generic site layouts with macroinvertebrate sampling locations in red. Seepage lakes have no true inlet or outlet stream. In flow-through streams, inlet and outlet infrastructure are located in the inlet or outlet stream channel. 11

Figure 11. Example of adhesive jar labels for macroinvertebrate sampling. 30

Figure 12. Example of adhesive barcode labels..... 31

Figure 13. Lake and river decision tree for choosing the appropriate sampler..... 33

Figure 14. Wadeable stream decision tree for choosing the appropriate sampler..... 34

Figure 15. Diagram of Surber sampler set-up. The inside of the base is the sample area of the stream bottom (0.09 m²)..... 35

Figure 16. Hold the Surber net on the stream bottom, and keeps the bucket nearby for depositing rocks from the base of the Surber..... 36

Figure 17. Cobble selection at Surber edges. The yellow square represents the bottom of the Surber sampler. 37

Figure 18. Scrub rocks from the Surber sample in the 3 gallon bucket..... 38

Figure 19. Removing the tip of the 500 mL wash bottle helps makes rinsing easier and increases water pressure. This tip pulls easily out of the main body of the wash bottle..... 38

Figure 20. Example of a petite ponar setup 40

Figure 21. Sites such as D08 Mayfield Creek are well-suited to snag sampling with their sandy/silty substrate and abundance submerged large woody debris. 41

Figure 22. From Angradi et al. 2006, example of snag sampling in a large river. While the boat driver holds the boat in position, one person holds the modified kicknet against the snag, while a second scrubs the snag with a long-handled deck brush..... 44

Figure 23. Hand-corer assembly: A) Disassembled corer. Use of the liner tube and core catcher are optional. B) Assembled corer. Note: the nosepiece may be stainless steel (not black Lexan as in photo) in some domains..... 45

Figure 24. Push the hand corer through the water and into the sediments at a 90° angle 46

Figure 25. Example of modified kicknet setup. 47

Figure 26. Hess sampler with collection net and dolphin bucket..... 49

Figure 27. Example of Riparian Stations splitting the lake into sections at D04 Lake Barco..... 50

Figure 28. D-frame net, used for sweep samples in vegetation and silty habitats. 51

Figure 29. D-frame sweep technique in a littoral area; the D-frame net must remain submerged and close to the substrate throughout the entire sweep..... 52

Figure 30. Process of elutriation (Dates and Byrne 1997)..... 54

Figure 31. Carefully pours water from the 3 gallon bucket into the sieve. 55

Figure 32. Rinse the sample from the sieve into the open container with the 500 mL wash bottle. 56

Figure 33. Barcode label scanning. 57

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

1 OVERVIEW

1.1 Background

Aquatic macroinvertebrates are a diverse and ubiquitous group of organisms (Hauer and Resh 2006). Streams and rivers harbor most major taxa of aquatic organisms, however some invertebrates occur only in lakes and ponds (Hynes 2001). Because of their presence in nearly all bodies of freshwater, aquatic macroinvertebrates are excellent study organisms to address questions of biodiversity. Aquatic invertebrates are easily sampled, common in all but the most polluted waters, and strongly affected by water quality.

Aquatic macroinvertebrates are an important part of the aquatic community. Most benthic macroinvertebrates are primary consumers and feed on autotrophic (algae, plants) and heterotrophic (leaf litter, dissolved organic carbon) production, while some benthic macroinvertebrates are predators. In general, benthic macroinvertebrates are important vectors of energy transfer from one trophic level to the next (e.g., from sunlight + nutrients → primary producers → consumers → predators). Macroinvertebrates can be classified into functional feeding groups based on morphological and behavioral mechanisms for food acquisition (Merritt and Cummins 2006), including scrapers (feed on algae; Figure 1), shredders (feed on leaf litter), collector-gatherers (feed on organic matter and other material), filter feeders (filter fine particles from the water column), and predators (feed on other macroinvertebrates).



Figure 1. Mayflies (Ephemeroptera: Heptageniidae) are scrapers that are adapted to feed most efficiently on attached periphyton in flowing waters.

Freshwater benthic macroinvertebrate communities are strongly affected by abiotic factors such as disturbance, shifts in nutrient concentrations, pollutants, temperature, and pH, as well as environmental factors such as scouring, freezing, flooding, drought, and biological factors such as vegetation structure and predation (Allan 1995, Wetzel 2001). Such sensitivity to environmental conditions makes benthic invertebrates ideal for use in monitoring programs such as the US Environmental Protection Agency Rapid Bioassessment Protocol (EPA RBP; Barbour et al. 1999) and US Geological Survey National Water-

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

Quality and Assessment Program (USGS NAWQA; Moulton et al. 2002). Members of the Ephemeroptera (mayflies), Plecoptera (stoneflies), and Trichoptera (caddisflies) are often thought to be the most sensitive taxa and when present in the aquatic habitat, can be indicators of good to excellent water quality. However, other taxa such as members of the family Chironomidae (midges, non-biting flies) and oligochaetes are ubiquitous and highly tolerant, and can be indicators of poorer water quality. Sampling stream and lake benthic communities over the time span of the NEON Observatory will help researchers determine changes in presence/absence of taxa, taxa diversity and richness, community structure, and species loss.

1.2 Scope

This document provides a change-controlled version of Observatory protocols and procedures. Documentation of content changes (i.e. changes in particular tasks or safety practices) will occur via this change-controlled document, not through field manuals or training materials.

1.2.1 NEON Science Requirements and Data Products

This protocol fulfills Observatory science requirements that reside in NEON’s Dynamic Object-Oriented Requirements System (DOORS). Copies of approved science requirements have been exported from DOORS and are available in NEON’s document repository, or upon request.

Execution of this protocol procures samples and/or generates raw data satisfying NEON Observatory scientific requirements. These data and samples are used to create NEON data products, and are documented in the NEON Scientific Data Products Catalog (RD[03]).

1.3 Acknowledgments

Benthic invertebrate protocols for **wadeable streams** are informed by the US Geological Survey (USGS) National Water Quality Assessment (NAWQA) program (Moulton et al. 2002), the US Environmental Protection Agency (EPA) Rapid Bioassessment Protocols (Barbour et al. 1999), and Arctic Long-Term Ecological Research (LTER) Protocols (Slavik et al. 2004). Benthic invertebrate protocols for **lakes and non-wadeable streams** are based on those of the US Environmental Protection Agency (USEPA) Environmental Monitoring and Assessment Program (EMAP) Program for Surface Waters (Baker et al. 1997), Standard Operating Procedure for Benthic Invertebrate Field Sampling (USEPA 2002), and the USEPA Great River Ecosystems Field Operations Manual (Angradi et al. 2006).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

2 RELATED DOCUMENTS AND ACRONYMS

2.1 Applicable Documents

Applicable documents contain higher-level information that is implemented in the current document. Examples include designs, plans, or standards.

AD[01]	NEON.DOC.004300	NEON EHSS Policy, Program and Management Plan
AD[02]	NEON.DOC.004316	Operations Field Safety and Security Plan
AD[03]	NEON.DOC.000724	Domain Chemical Hygiene Plan and Biosafety Manual
AD[04]	NEON.DOC.050005	Field Operations Job Instruction Training Plan
AD[05]	NEON.DOC.004104	NEON Science Performance QA/QC Plan

2.2 Reference Documents

Reference documents contain information that supports or complements the current document. Examples include related protocols, datasheets, or general-information references.

RD[01]	NEON.DOC.000008	NEON Acronym List
RD[02]	NEON.DOC.000243	NEON Glossary of Terms
RD[03]	NEON.DOC.002652	NEON Level 1, Level 2, Level 3 Data Products Catalog
RD[04]	NEON.DOC.001271	NEON Protocol and Procedure: Manual Data Transcription
RD[05]	NEON.DOC.003043	Datasheets for AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling
RD[06]	NEON.DOC.001646	General AQU Field Metadata Sheet
RD[07]	NEON.DOC.001152	NEON Aquatic Sample Strategy Document
RD[08]	NEON.DOC.004257	NEON Standard Operating Procedure (SOP): Decontamination of sensors, field equipment and field vehicles
RD[09]	NEON.DOC.003162	AOS Protocol and Procedure: Wadeable Stream Morphology
RD[10]	NEON.DOC.014050	TOS Protocol and Procedure: Ground Beetle Sampling
RD[11]	NEON.DOC.002494	Datasheets for AOS Sample Shipping Inventory
RD[12]	NEON.DOC.003045	AOS Protocol and Procedure: Periphyton and Phytoplankton Sampling
RD[13]	NEON.DOC.003039	AOS Protocol and Procedure: Aquatic Plant, Bryophyte, Lichen, and Macroalgae Sampling
RD[14]	NEON.DOC.003044	AOS Protocol and Procedure: Aquatic Microbial Sampling
RD[15]	NEON.DOC.001195	AOS Protocol and Procedure: Riparian Habitat Assessment in Lakes and Non-wadeable Streams
RD[16]	NEON.DOC.001197	AOS Protocol and Procedure: Bathymetry and Morphology of Lakes and Non-wadeable Streams
RD[17]	NEON.DOC.001194	AOS Protocol and Procedure: Zooplankton Sampling in Lakes

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

2.3 Acronyms

Acronym	Definition
cm	centimeter
DNA	Deoxyribonucleic acid
EMAP	Environmental Monitoring and Assessment Program
FFG	Functional feeding group
ft	Foot
GPS	Global Positioning System
hr	Hour
Km	kilometer
LTER	Long Term Ecological Research Program
m	Meter
µm	micrometer
mL	milliliter
mm	millimeter
NAWQA	National Water-Quality Assessment (USGS)
NEON	National Ecological Observatory Network
NLA	National Lakes Assessment
PFD	Personal Flotation Device
qt	Quart
RBP	Rapid Bioassessment Protocol (US EPA)
s	second
USEPA	US Environmental Protection Agency
USGS	US Geological Survey

2.4 Definitions

Autotroph: (Primary producers) Organisms that acquire energy from non-living inorganic sources.

Benthic: The region in or near the sediments or bed of a body of water (e.g., bottom of the stream).

Caddisflies: Aquatic invertebrates in the Phylum Insecta, Order Trichoptera. Larvae of most species build a case out of sand or small pieces of wood around the soft, larval body (Figure 2), or spin a net to capture suspended particles in the water column.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 2. Caddisflies (Trichoptera) often build cases out of small pebbles, sand, or pieces of small woody debris.

Clams: Benthic mollusks sometimes found in the sediments of streams and lakes, with a shell composed of two hinged shell, thus “bivalves” and similar to mussels. Clams are filter feeders.

Collector-gatherer: (Functional feeding group) Invertebrates that are morphologically adapted to feed on a variety of items, including coarse detritus and periphyton.

Consumers: (Trophic level) Mid-levels of the food chain, organisms that consume primary producers and detritus.

D-frame net: Collecting net with handle. The net frame is shaped like a ‘D’, allowing the net to be placed against a stream or lake bottom. The D-frame net has a 30 cm wide opening and 243 μm Nitex mesh collection net with handle.

Filter feeder: (Functional feeding group) Invertebrates that are morphologically adapted to feed by straining suspended particles from the water column (Figure 3). In streams, filter feeders are typically attached to the substratum (e.g., blackflies, mussels).



Figure 3. Black fly (Diptera: Simuliidae) larva, an invertebrate that uses fanlike mouthparts to strain particulates from moving water.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Functional feeding group (FFG): Benthic invertebrate groupings based on morphological and behavioral mechanisms for food acquisition (includes scrapers, filter-feeders, collector-gatherers, predators, and shredders).

Hand corer: Benthic sampler for sand- and silt-bottomed streams (Figure 23). Sampler consists of an inner PVC tube and an outer, stainless steel housing for pushing the corer into the substratum. The stainless steel barrel is 5 cm in diameter by 50 cm high with a handle on top.

Hess sampler: Benthic sampler for gravel-bottomed streams (Figure 26). Sampler consists of a stainless steel drum fitted with a flow-through collection net. The drum is 33 cm in diameter by 40 cm high, with a 243 µm Nitex mesh net.

Heterotroph: Organisms that acquire energy from living or non-living sources of organic matter.

Invertebrate: Animal without a backbone. Most stream invertebrates have an exoskeleton, including mussels, snails, crayfish, insects, and zooplankton.

Large woody debris: Downed woody debris submerged in the stream/river that is ≥0.3 m (6 inches) in diameter at the large end and ≥ 5 m long (Angradi et al. 2006).

Leaf litter: Terrestrial leaves that have fallen into the stream channel, where they are colonized by bacteria and fungi.

Littoral: Near-shore area of the lake/river, extends from the high-water mark to the shallow, submerged area of the lake/river; typically, the area near shore where sunlight reaches the bottom.

Macroinvertebrate: Typically refers to benthic invertebrates that are >500 µm in length. For the purposes of this protocol, benthic invertebrates >250 µm will be considered macroinvertebrates.

Modified kicknet: Benthic sampler used for faster and deeper water (runs). The modified kicknet has a 33 x 5- cm frame with 243 µm Nitex mesh net attached, and a long handle for holding the net in fast current (Figure 25).

Mollusks: A large phylum of invertebrates, freshwater mollusks often have a soft body surrounded by a shell. This group includes snails, mussels, and clams in freshwaters.

Mussels: Benthic mollusks often found in the sediments of streams and lakes, with a shell composed of two hinged shell, thus “bivalves” (Figure 4). Mussels are filter feeders.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 4. Freshwater mussels are often found in streams. Pictured here, lampmussels (*Lampsilis virescens*) from Alabama.

Petite ponar: Benthic sampler used for soft sediments in deep and slow-moving water. The Ponar consists of 2 steel halves that close when the sampler reaches the sediment, grabbing a 6"x6" area of sediment (Figure 20).

Pool: An aquatic habitat unit in a river or stream created by local scour or impoundment and having a structural control. Pool water depth is above average, if all the running water in the stream was shut off, areas in the stream that would still hold water are pools. Pool water velocity is below average for the reach and because of that fine sediments deposit in pools. Pools are generally longer than they are wide (unless they are plunge pools), and are 1.5 x deeper at their maximum depth than they are at their crest.

Predator: (Functional feeding group and trophic level) Animals that eat other animals. In stream communities, predators include insects, fish, and birds; higher level of the food chain (Figure 5).



Figure 5. A mayfly predator feeding on another aquatic invertebrate.

Primary producers: (Trophic level) Lowest level of the food chain, organisms that use sunlight and nutrients to create energy.

Riffle: Shallow reaches flowing over rough bed material such as boulders and cobbles, creating ripples, waves, and eddies on the water surface.

Run: An aquatic habitat with swiftly flowing water but no surface water agitation, with relatively uniform flow.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Scraper: (Functional feeding group) Invertebrates morphologically adapted to feed by scraping algae and periphyton off surfaces (e.g., rocks or plant surfaces; Figure 6).



Figure 6. Mayfly scrapers feeding on a rock surface.

Shredder: (Functional feeding group) Invertebrates morphologically adapted to feed by shredding leaf litter, aquatic plants, and coarse organic matter (Figure 7).



Figure 7. A stonefly shredder feeding on plant detritus in a stream.

Snag (woody snag): Submerged woody debris in the stream channel that often provides substratum and refuge for macroinvertebrates, often associated with other organic matter such as leaf packs (Moulton et al. 2002). For the purposes of this protocol, woody snags are considered to be smaller than large woody debris (LWD).

Snails: Mollusks, members of the class Gastropoda (literally “stomach foot”), snails typically have a coiled shell around a soft body (Figure 8). Aquatic snails are often found in streams or lakes.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 8. *Elimia* is a genus of snail often found in rivers and streams.

Step pool: High-gradient streams (steep) where water cascades over a rock or woody snag, dropping into a pool. Due to the gradient and surrounding geology, this pattern continues down the stream: step (drop)—pool—step—pool—etc. (Figure 9).



Figure 9. Step pools occur in high-gradient streams where there are channel-spanning pools separated by boulder/cobble steps.

Surber sampler: Benthic sampler for flowing waters. A standard Surber sampler consists of a 30 cm x 30 cm frame and a long 243 μ m Nitex mesh net that collects organisms (Figure 15).

Thalweg: The portion of the stream channel through which the majority of the stream flow is transported. This is typically identified as the deepest portion of the flowing channel.

Trophic level: Step in the transfer of energy within a food chain or food web.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

3 METHOD

The goal of benthic invertebrate sampling is to determine taxa diversity, the number of species present (richness), biomass, and to enable DNA analysis (addressed in RD[09]) for benthic invertebrates at each aquatic sampling site. These variables, especially diversity and biomass, will be tracked over time to detect changes in species loss, changes in community structure and function, as well as the introduction and the spread of invasive taxa (presence/absence).

Benthic invertebrates at NEON aquatic sites are sampled using a percent-based macrohabitat approach (after Moulton et al. 2002). Habitats sampled focus on riffles, runs, and pools depending on the percent cover of each habitat within each 1 km-long NEON Aquatic **wadeable stream** site (NOTE: some NEON sites may be less than 1 km due to permitting restrictions), and pelagic and littoral samples in **lakes and non-wadeable streams (or rivers)**. Five samples are collected in the dominant habitat type (**wadeable stream**) or littoral area (**lake and river**), and three samples are collected in the second-most dominant habitat type (**wadeable streams**) or pelagic area (**lakes and rivers**) for a total of eight samples on a given sampling date at a site. Field protocols differ depending on the habitat and substrate being sampled. However, all samples are collected from the surface of the natural substratum in each habitat. In **wadeable streams**, the majority of the invertebrate community is likely to colonize riffles and runs, while in sandy and silty habitats and in pools invertebrates are likely to be most diverse on woody debris. In **lakes and rivers**, macroinvertebrates are likely to be most diverse in littoral aquatic plant beds. Appropriate site-specific sampling procedures will be determined prior to sampling and documented in the Site-Specific Sampling Design document. Samples are collected by field personnel then preserved and sent to taxonomists for identification.

Macroinvertebrate sampling occurs three times per year. Timing of sampling is site-specific and determined based on historical hydrological and meteorological data. Specific details on sample dates are provided in the NEON Aquatic Sample Strategy Document (RD[07]) and Appendix D. Sample bout 1 is an early-season date, representing a period of rapid biomass accumulation after winter, typically prior to leaf out or ice-off where applicable. Sample bout 2 targets mid-summer baseflow conditions and sample bout 3 represents the late growing season (typically autumn) during leaf-fall where applicable. These dates will differ on a site-by-site basis, but should always occur at, or near, baseflow conditions within the watershed. Sampling will not occur directly following a flood in **wadeable streams** (defined as $>1.5 \times$ base flow; Biggs et al. 1999). Should such a flood event occur on or prior to a target collection date, sampling should be delayed at least 5 days to allow for invertebrates to recolonize the substratum (c.f. Brooks and Boulton 1991, Matthaei et al. 1996).




Figure 10. Generic site layouts with macroinvertebrate sampling locations in red. Seepage lakes have no true inlet or outlet stream. In flow-through streams, inlet and outlet infrastructure are located in the inlet or outlet stream channel.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

Standard Operating Procedures (SOPs), in Section 7 of this document, provide detailed step-by-step directions, contingency plans, sampling tips, and best practices for implementing this sampling procedure. To properly collect and process samples, field technicians **must** follow the protocol and associated SOPs. Use NEON’s problem reporting system to resolve any field issues associated with implementing this protocol.

The value of NEON data hinges on consistent implementation of this protocol across all NEON domains, for the life of the project. It is therefore essential that field personnel carry out this protocol as outlined in this document. In the event that local conditions create uncertainty about carrying out these steps, it is critical that technicians document the problem and enter it in NEON’s problem tracking system.

Quality assurance will be performed on data collected via these procedures according to the NEON Science Performance QA/QC Plan (AD[05]).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

4 SAMPLING SCHEDULE

4.1 Sampling Frequency and Timing

Benthic invertebrate sampling in lakes, non-wadeable and wadeable streams occurs three times per year at each site, roughly spring, summer, and autumn. Sampling must be scheduled within the first 21 days of the 1 month window specified in Appendix D with a minimum of two weeks between sampling dates. Accommodations for local weather conditions (e.g., late ice-off) may be made that cause the sample date to fall outside of the pre-determined window. Use NEON’s problem reporting system to report sampling efforts that take place outside of the defined sampling window.

4.2 Criteria for Determining Onset and Cessation of Sampling

A range of dates for each site were determined *a priori*, based on historical data including ice on/ice off, streamflow, the accumulation of degree days, weather, and riparian phenology (Appendix D).

4.3 Timing for Laboratory Processing and Analysis

Macroinvertebrate samples must have their preservative changed after field collection, and before sending to the macroinvertebrate taxonomist. Preservative must be changed within 12-72 hours of field sampling. Samples must be shipped to the external lab within 30 days of collection. For additional storage and shipping timelines see SOP G.

4.4 Sample Timing Contingencies

All samples from this protocol in one sampling bout must be collected within one day (i.e., all 8 samples per stream or all samples per lake/rivers as detailed in this protocol) because of the fluctuating nature of aquatic habitats. Spreading sample collection over multiple days increases variability among samples. A minimum of 2 weeks between sample periods shall be observed. Sampling may extend past the end of the bout window if weather and flow conditions necessitate. Sampling should not be canceled unless the date is within 2 weeks of the start of the next bout window, the site is frozen which prohibits sampling (Bout 3 only), or you have reached the end of the calendar year.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Table 1. Contingent decisions

Delay/ Situation	Action	Outcome for Data Products
Hours	If weather conditions deteriorate and conditions become unsafe (e.g. approaching thunderstorm, rapid increase of water level in the wadeable stream), or the lake/river becomes too windy (>32 km hr ⁻¹) and has unsafe wave heights (>1 m) so that the boat cannot be held stationary over a sampling point while at anchor, return to shore and wait in a safe location for 30 minutes. If conditions improve, resume sampling, if not, return to the Domain Support Facility and sample at another time.	None as long as samples are collected within the pre-determined sampling window. If waiting for favorable conditions causes sampling to occur outside of the sampling window, data must be flagged.
	If circumstances occur that delay sampling (e.g., lightning), but sampling can be continued the same day while still meeting the streamflow or weather requirements below, continue to collect samples after the delay. If conditions do not improve, discard any previously collected samples at the site or at the Domain Support Facility and start over on the next appropriate sampling day.	None as long as samples are collected within the pre-determined sampling window. If waiting for favorable conditions causes sampling to occur outside of the sampling window, data must be flagged.
5 Days	If flooding occurs on or prior to the targeted sampling date in a wadeable stream (>3x median discharge for the preceding year; Clausen and Biggs 1997) or unsafe wading conditions occur (Lane and Fay 1997), wait a minimum of 5 days after water level drops below 3x median discharge and is safely wadeable to allow the invertebrate community to recolonize.	None as long as samples are collected within the pre-determined sampling window. If waiting for flooding to diminish causes sampling to occur outside of the sampling window, data must be flagged.
6 Months	Preserved macroinvertebrate samples may be held for up to 6 months at room temperature or 4 °C in the domain lab if circumstances do not allow shipping to the external lab.	Holding samples >30 days affects external lab schedules, staffing, and budgets and delays data release on the NEON portal. However, sample integrity is not affected and samples do not need to be flagged if held for ≤6 months.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

4.5 Criteria for Permanent Reallocation of Sampling Within a Site

Macroinvertebrate sampling will occur on the schedule described above at 8 locations per site in two different habitat types. Ideally, sampling will occur at these sampling locations for the lifetime of the Observatory (core sites) or the duration of the site’s affiliation with the NEON project (relocatable sites). However, circumstances may arise requiring that sampling within a site be shifted from one particular location to another. In general, sampling is considered to be compromised when sampling at a location becomes so limited that data quality is significantly reduced. If sampling at a given location becomes compromised, a problem ticket should be submitted by Field Operations to Science.

There are two main pathways by which sampling can be compromised. Sampling locations can become inappropriately suited to answer meaningful biological questions (e.g., a terrestrial sampling plot becomes permanently flooded or a stream channel moves after a flood). Alternatively, sampling locations may be located in areas that are logistically impossible to sample on a schedule that is biologically meaningful.

A common occurrence in macroinvertebrate sampling is loss of habitat due to channel drying or permitting restrictions. Contingent decisions in Table 2 should be followed if the wetted area of sampling is decreased, and a problem ticket should be submitted. If water returns to the reach, full sampling should resume. Shifting of the stream channel is expected and does not necessarily compromise sampling.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Table 2. Contingent decisions for sampling in a wadeable stream.

Situation	Action	Outcome for Data Products	Considerations
<u>Wadeable stream</u> site with <500 m aboveground stream length due to stream size or permitting restrictions	Habitat available may be insufficient to accommodate all 8 samples without causing harm to the stream. Reduce sampling by collecting samples only in the dominant habitat type (5 samples total). Enter “sampling impractical” for the missing habitat type.	Lower resolution for diversity metrics.	If the decision is made to decrease the number of samples collected for this protocol, it must also be reflected in the other wadeable stream biology protocols (RD[12], RD[13], RD[14]).
<u>Wadeable stream</u> site with seasonal drying	If the stream experiences seasonal drying such that the chosen habitat types have disappeared, select the next dominant habitat type in Figure 14, or use the sub-dominant habitat if still present. Reduce sampling by collecting samples only in the dominant habitat type (5 samples total). Enter “sampling impractical” for the missing habitat type.	Less standardization of the dataset.	Habitat types sampled should be present throughout the year. The decision to switch habitat types should only occur during periods of extreme drying such that typical habitat types are no longer present at the site.

4.6 Sampling Specific Concerns

1. Macroinvertebrates often become trapped in the folds of the nets (near the stitching). Check net seams between each sample to ensure that specimens are added to the correct samples, and do not remain in the net.
2. Macroinvertebrates are often lodged in the edges of the sieve. Check the sieve between samples to avoid sample-to-sample specimen contamination.
3. Samples must be preserved in the field within 1 hour of sampling to prevent predation within the sample, as predatory insects tend to eat smaller insects when put into sample jars.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

4.7 Safety

This document identifies procedure-specific safety hazards and associated safety requirements. It does not describe general safety practices or site-specific safety practices.

Personnel working at a NEON site must be compliant with safe field work practices as outlined in the Operations Field Safety and Security Plan (AD[02]) and EHS Safety Policy and Program Manual (AD[01]). Additional safety issues associated with this field procedure are outlined below. The Field Operations Manager and the Lead Field Ecologist have primary authority to stop work activities based on unsafe field conditions; however, all employees have the responsibility and right to stop their work in unsafe conditions.

Safety Data Sheets (SDS) shall be made available for all chemicals used in this work (ethanol). Whenever chemicals are used, follow requirements of the site-specific Chemical Hygiene and Biosafety Plan (AD[03]) for laboratory safety and NEON EHS Safety Policy and Program Manual (AD[01]), Section HC-03, Hazard Communication.

See Section 10 in the NEON Operations Field Safety and Security Plan (AD[02]) for aquatic-specific field safety requirements. In addition, the following safety requirements must be followed:

1. Activities in **wadeable streams** should only be performed when flow conditions are safe. Do not attempt to wade a stream where velocity x depth is $\geq 10 \text{ ft}^2/\text{s}$ ($0.93 \text{ m}^2/\text{s}$; Lane and Fay 1997).
2. In **lakes and rivers**, site-specific hazards may be encountered that necessitate sampling from the boat, without dismounting from the vessel. In addition, use extra caution in waters where alligators are present and maintain a safe distance from hazards.
3. All personnel must be wearing a personal flotation device (PFD) prior to entering a boat.
4. All personnel shall have access to a form of communication with other team members such as a two-way radio.
5. Be aware of any site-specific hazards and to the waters of that particular location (i.e. current status, tidal charts, water release from dams, etc.).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

5 PERSONNEL AND EQUIPMENT

5.1 Equipment

The following equipment is needed to implement the procedures in this document. Equipment lists are organized by task. They do not include standard field and laboratory supplies such as charging stations, first aid kits, drying ovens, ultra-low refrigerators, etc.

Table 3. Equipment list – General equipment

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
Durable items								
RD[09], RD[15], RD[16]			R	Site-specific Rapid Habitat Assessment or Riparian Sampling Locations	Determining sampling locations	All	1	N
MX111388	CDW-G	4452963	R	Mobile data entry tablet	Field data entry	All	1	N
			S	Cooler, 9-28 qt	Field sample storage; use size appropriate to samples being collected	All	1	N
MX100491 MX100494 MX107505	Ben Meadows Co., Inc. Grainger, W.W. Forestry Suppliers, Inc. Cabela's		R	Waders (hip or chest) or knee boots	Wading	All	1 pair/person	N

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
			R	Personal flotation device (PFD)	Boating safety	Lakes/non-wadeables	1 per person	N
MX110075 MX102739	Forestry Suppliers, Inc. Cabela's Inc. Recreational Equipment Inc.	39481 IK-270217 895022	R	Handheld GPS unit (with batteries, ±4 m accuracy) or Humminbird	Navigating to sampling locations	Lakes/non-wadeables	1	N
MX100453	West Marine Products, Inc.	15131444	R	Depth finder (see Bathymetry Protocol, RD[17])	Determining depth at sampling location	Lakes/non-wadeables	1	N
Consumable items								
RD[06]			R	General AQU Field Metadata Sheet	Recording metadata in case tablet fails	All	1	N
RD[05] MX103942	Ben Meadows Co., Inc. Forestry Suppliers, Inc.	010510-1 49247	R	Field data sheets (all-weather copier paper, write in pencil)	Recording data in case tablet fails	All	5 sheets	N
MX103942	Ben Meadows Co., Inc. Forestry Suppliers, Inc.	010510-1 49247	R	Pre-printed paper labels (all-weather copier paper, write in pencil)	Labeling samples, inside sample jar	All	1 sheet	N

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
MX106268	Amazon Capital Services Inc.	7530-01-498-9209	R	Pre-printed 1" x 2 5/8" adhesive labels (write in permanent marker)	Labeling samples, outside sample jar	All	1 sheet	N
			S	Adhesive barcode labels	Labeling sample bottles with barcode-readable	All	1 sheet	N
			R	Pencils	Recording data	All	4	N

R/S=Required/Suggested

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Table 4. Equipment list – Macroinvertebrate Samplers

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
Durable items								
MX100305	Ben Meadows Co., Inc.	227439	R	Surber sampler (243 μ m Nitex mesh), 0.093 m ²	Sample collection in riffles	Wadeables	1	N
MX108051	Ben Meadows Co., Inc.	227441	R	Hess sampler (243 μ m Nitex mesh), 0.086 m ²	Sample collection in riffles, runs, shallow pools	Wadeables	1	N
MX100303	Ben Meadows Co., Inc.	223578	R	Petite ponar sampler with rope	Sample collection in soft sediments	Lakes/Non-wadeables	1	N
			S	Messenger	Used with petite ponar	Lakes/Non-wadeables	1	N
MX100309	Ben Meadows Co., Inc	223583	R	Hand corer, stainless steel, 20 in	Sample collection in sandy or silty habitats (streams)	Wadeables	1	N
MX108199	Ben Meadows Co., Inc.	227442	R	Modified kicknet sampler (rectangular, 243 μ m Nitex mesh)	Sample collection in runs (streams) and large woody debris	Wadeables, Non-wadeables	1	N
MX100304	Ben Meadows Co., Inc.	279992	R	Collapsible quadrat (0.5 x 0.5 m ²)	Used with modified kicknet sampler in streams	Wadeables	1	N

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
MX102972	Ben Meadows Co., Inc.	425D21	R	D-frame net (243 µm Nitex mesh)	Sample collection for woody snags and littoral (lakes/rivers)	All	1	N
MX104436 MX110541	Forestry Suppliers, Inc. Home Depot	75080 643278	S	Bow saw, 21 in or loppers	Used with D-frame snag sampler in streams	Wadeables , Non-wadeables	1	N
			S	Work Gloves (pair)	Used with petite ponar for safe handling of ponar rope	Lakes/Non-wadeables	1	N
MX105823 MX100326	Forestry Suppliers, Inc. Fisher Scientific Company, LLC	71112 S90532C	R	Meter stick, meter tape, or metric ruler	Used with snag and LWD samplers (streams and lakes/rivers)	All	1	N
MX101220	Grainger, W.W.	2RWC7	R	Kitchen brush with nylon bristles	Used with Surber, Hess, snag, and LWD samplers for rock and wood scrubs	All	2	N
MX110474 MX110477	Grainger, W.W.	3H382 3H384	R	Deck brush with polypropylene bristles, 60 inch handle	Used with LWD/modified kicknet sampler	Non-wadeables	1	N

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
MX101529	Grainger, W.W.	4YP29	S	Putty knife	Scrape plant material off cobbles	Wadeables	1	N
Consumable items								
MX106276	Amazon Capital Services Inc.	B001ECQ4L2	S	Petroleum jelly	Used with hand corer to maintain suction	Wadeables	1	N

R/S=Required/Suggested

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Table 5. Equipment list – Macroinvertebrate field elutriation and preservation

Item No.			R/S	Description	Purpose	Quantity	Special Handling
Durable Items							
MX100308	Fisher Scientific Company, LLC	0340910E	R	Polyethylene wash bottle, unitary (500 mL; Figure 19)	Rinsing sieve, bucket	2	N
MX100306	Ben Meadows Co., Inc.	134576	R	Sieve, 250 µm	Sample sieving; elutriation	1	N
MX109110	Ben Meadows Co., Inc.	217009	S	Sieve bucket, 242 µm	Sample sieving; elutriation in <u>lakes/streams</u>	1	N
MX100526	Grainger, W.W.	34A216	R	Plastic bucket, 3 or 5 gallon	Substrate scrubbing (streams), elutriation, collecting waste water on boat (lake/river)	1-2	N
MX102975	BioQuip Products Inc.	4748	S	Flexible forceps, featherweight	Collecting clinging insects	1	N
MX100665 MX100345 MX105571	Thomas Scientific, Inc.	1709C04 (clear) 1185B56 (amber) 1212W94 (clear jug)	R	HDPE bottles (1 L) or jug (4 L) with lids (clear or amber)	Transporting ethanol to the field	1-4	N
Consumable Items							

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Item No.			R/S	Description	Purpose	Quantity	Special Handling
MX110492 MX108207 MX109111	United States Plastic Corp	66286 66027 66028	R	Sample jars, HDPE with screw-top lid, 6, 16, or 32 oz.	Sample container, field staff choose sizes appropriate for site	8	N
MX103145	Amazon Capital Services Inc.	B005IQTSE0	S	Disposable pipets (polyethylene), 3 mL	Collecting clinging insects	2	N
MX100213 MX100202	Fisher Scientific Company Thomas Scientific, Inc.	4355601 C954K61	R	Ethanol, 95% non-denatured	Preservative	1-4 L	Y
			S	Latex or Nitrile gloves (pair)	Preventing preservative contact with skin	5	N
MX104844	Grainger, W.W.	5LH30	S	Resealable plastic zip-top bags (gallon)	Organizing samples	5	N

R/S=Required/Suggested

Table 6. Equipment list – Laboratory processing: preservative replenishment

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Quantity	Special Handling
Durable items							

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Quantity	Special Handling
MX100308	Fisher Scientific Company, LLC	0340910E	R	Unitary wash bottle, 500 mL, ETOH + glycerol	Adding preservative to sample jars and rinsing filter cup	1	Y
MX100306	Ben Meadows Co., Inc.	134576	S	Sieve, 250 µm	Changing preservative	1	N
MX100652 MX107766	Fisher Scientific Company, LLC Amazon Capital Services Inc.	033134E 24-C44	R	Filter cup (500 mL HDPE bottle and 243 µm Nitex mesh square, see TOS beetle protocol)	Changing preservative	1	N
MX102975	BioQuip Products Inc.	4748	S	Featherweight forceps	Picking up insects	1	N
			R	Safety glasses	Preventing preservative contact with eyes	1 pair	N
Consumable items							
MX100213 MX100202	Fisher Scientific Company Thomas Scientific, Inc.	4355601 C954K61	R	Ethanol, 95%, undenatured	Preservative	5 L	Y
MX106344	Fisher Scientific Company	g331	R	Glycerol, >99%	Preservative	1 L	Y
MX107766	Amazon Capital Services Inc.	24-C44	R	243 µm Nitex mesh cloth, cut into squares for filter cup	Catching insects over the filter cup	8	N

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Quantity	Special Handling
			R	Nitrile gloves	Preventing preservative contact with skin	1 pair	N

R/S=Required/Suggested

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

Table 7. Equipment list – Shipping supplies

Item No.	Supplier	Supplier ID	R/S	Description	Purpose	Quantity	Special Handling
Durable Items							
Consumable Items							
			R	Cardboard box, UN-rated, Group II	Shipping samples to taxonomist	1	N
MX109205	Grainger, W.W.	30RD13	R	Vermiculite, Grade 2	Absorbing liquid leaks and cushioning shipment	TBD	N
MX102717	Uline	S-5106	R	Heavy duty plastic trash bag	Lining the shipping container	1	
MX101876	Grainger, W.W.	2A227	R	Electrical tape	Sealing jar lids prior to shipping	1 roll	N
AD[03]			R	Appropriate labels and forms for limited quantity ground shipments	Shipping paperwork and external shipping labels	TBD	N
RD[11]			R	Shipping inventory	Provides sample information to external lab	1	N

R/S=Required/Suggested

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

5.2 Training Requirements

Field staff must complete protocol-specific training for safety and implementation of this protocol as required in Field Operations Job Instruction Training Plan (AD[04]).

All personnel required to operate a boat shall be trained through an approved program. All other personnel using a boat shall be aware of boating safety procedures.

Personnel will be trained in field protocols associated with this document, and trained in safe working practices for aquatic field work. Personnel must also be trained in safe handling of ethanol as required in the Domain Chemical Hygiene Plan and Biosafety Manual (AD[03]).

5.3 Specialized Skills

Where applicable, personnel will be licensed to operate a boat and able to safely handle a motor and drive a boat safely.

5.4 Estimated Time

The time required to implement a protocol will vary depending on a number of factors, such as skill level, system diversity, environmental conditions, and distance between sample plots. The timeframe provided below is an estimate based on completion of a task by a skilled two-person team (i.e., not the time it takes at the beginning of the field season). Use this estimate as framework for assessing progress. If a task is taking significantly longer than the estimated time, a problem ticket should be submitted. Please note that if sampling at particular locations requires significantly more time than expected, Science may propose to move these sampling locations.

Field sampling requires two field ecologists for four hours per site, plus travel to and from the site. Lab processing requires one ecologist for one to two hours within 12-72 hours of field sampling.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

6 STANDARD OPERATING PROCEDURES

SOP A Preparing for Sampling


A.1 Preparing for Data Capture

Mobile applications are the preferred mechanism for data entry. Mobile devices should be fully charged and synced at the beginning of each field day, whenever possible.

However, given the potential for mobile devices to fail under field conditions, it is imperative that paper datasheets are always available to record data. Paper datasheets should be carried along with the mobile devices to sampling locations at all times.

A.2 Macroinvertebrate Field Sampling

1. Collect and prepare all equipment, including sample jars and labels: paper (inside jar) and adhesive/barcode (outside jar) (RD[05], Figure 11).
2. Load GPS sampling coordinates on handheld GPS unit.
3. Check nets and sieves for holes, repair if necessary. Ensure that both are clean and free of debris and organic matter.
4. If using a hand corer in **wadeable streams**, mark 5 and 10 cm from the bottom of the barrel with permanent marker. The contents of the nosepiece are not contained in the final sample.
5. Fill 1 L HDPE bottles (or 4 L HDPE jug) with 95% ethanol (Stein et al. 2013). Cap tightly. Clearly label bottle and transport to the field following EHS guidelines.
6. Fill out general aquatic field metadata mobile app upon every field sampling visit. If other protocols are done in the same day, one record for field metadata for the day is sufficient.



NEON DNA ETOH preserved
 Sample ID: ARIK.20170928.kicknet.1
 Sample type: surber mini surber snag LWD
 core kicknet hess ponar benthic sweep floating sweep
 Collected by: sparker

NEON DNA ETOH preserved
 Sample ID: ARIK.20170928.kicknet.1.DNA
 Sample type: surber mini surber snag LWD
 core kicknet hess ponar benthic sweep floating sweep
 Collected by: sparker

Figure 11. Example of adhesive jar labels for macroinvertebrate sampling.

7. When the system is available, adhesive barcode labels will be added to the sample containers and scanned by the mobile app (Figure 12). Add adhesive labels to macroinvertebrate jars prior to getting in the field and getting the bottle wet.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- a. Keep a human-readable label on each bottle with a minimum of the sample ID printed to assist with organization and shipping.



Figure 12. Example of adhesive barcode labels.

- 8. Human-readable sample IDs will be generated by the mobile app as follows (
- 9. Table 8). Sample IDs written on the physical sample label must match the sample ID generated by the mobile app.

Table 8. Examples of sample IDs generated by the mobile app.

Sampler type	Site type	Field app populates as:	Example Sample ID
Surber	Stream	surber	MAYF.20161027.surber.1
Core	Stream	core	MAYF.20161027.core.1
Hess	Stream	hess	MAYF.20161027.hess.1
Modified kicknet	Stream	kicknet	MAYF.20161027.kicknet.1
Petite Ponar	Stream, lake, river	ponar	CRAM.20161027.ponar.1
Snag, D-frame	Stream, River	snag	MAYF.20161027.snag.1
Mini Surber	Stream	miniSurber	MAYF.20161027.miniSurber.1
Benthic Sweep, D-frame	Lake, River	benthicSweep	CRAM.20161027.benthicSweep.1
Floating Sweep, D-frame	Lake, River	floatingSweep	CRAM.20161027.floatingSweep.1
LWD, Modified kicknet	Stream, River	lwd	TOMB.20161027.lwd.1

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

SOP B Determining Sampling Locations and Sampler Type

NEON aquatic macroinvertebrate sampling is intended to be quantitative. Although different sampler types may be used (see SOPs below) depending on the habitat and substrate at a site, the data produced are quantitative and thus will be comparable after ingest and processing.

B.1 Lakes and Rivers

1. Do not sample within a 5 m radius of the aquatic instrumentation.
2. Benthic sampling
 - a. **Lakes:** Benthic petite ponar samples (Section C.2) will be collected near aquatic chemistry sampling locations in lakes: at the buoy, inlet, and outlet.
 - b. **Rivers:** Benthic petite ponar samples (Section C.2) will be collected downstream of the buoy (≥ 5 m), two other deep-water locations within the 1 km reach.
 - i. If sampling a **river** with rocky substrata, use the modified kicknet method in Section C.6 (Figure 13).
3. Littoral sampling
 - a. Samples will be collected in 5 of 10 pre-defined riparian sections (RD[09]) based on the dominant substratum (e.g., submerged plants) in each section.
 - i. A section is the littoral area between the riparian sampling coordinates.
 - ii. Move to the next riparian section if the appropriate substratum type is not present in the chosen section.
 - b. The substratum type chosen should be present during all sampling bouts and account for at least 20% of the littoral area, ensuring that there is enough of the same substrata in which to collect all samples.
 - c. All 5 samples must be collected from the same substratum type on each sampling bout, unless a major event (i.e., a flood) causes significant changes to the substrata.
 - i. Document changes in sampler and substratum availability through NEON's problem tracking system.
 - d. Choose the appropriate sampler based on the field conditions and substrata being sampled.
 - e. The order of preference for sampling substrata is as follows (Figure 13), habitat suggestions for NEON sites can be found in Appendix E:
 - i. Aquatic plant beds, living or dead, or floating mats (D-frame net, Section C.8)
 - ii. Snags and Large woody debris (Snag and Large Woody Debris Sampling, Section C.3)

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C




Figure 13. Lake and river decision tree for choosing the appropriate sampler.

4. Do not sample anywhere you or other people/animals have recently disturbed (via sampling, walking, driving a boat, etc.) or locations that appear recently disturbed (e.g., overturned rocks, footprints, dislodged plants, other evidence of wildlife, cattle, humans, etc.).

B.2 Wadeable Streams

1. Do not sample within a 5 m radius of the aquatic instrumentation.
2. Determine the dominant habitat and second-most dominant habitat based on the Stream Morphology Map (RD[09]) or rapid habitat assessment (RD[09], SOP F) for the site. Habitat suggestions for NEON sites are provided in Appendix E.
 - a. The habitat types chosen should be present during all sampling bouts, and should account for at least 20% of the habitat area in the permitted reach as determined by the Rapid Habitat Assessment (RD[09]). The 20% cutoff ensures that there is enough habitat in which to collect all samples.
 - b. All 5 dominant samples must be collected from the same habitat type on each sampling bout and all 3 subdominant samples must be collected from the sample habitat type on each sampling bout, unless a major event (i.e., a flood or dewatering of the stream) causes significant changes to the stream channel and the habitat type is no longer present.
 - c. If there is only one clear habitat at the site, sample two different types of substrata using the sampling methods below (e.g., in a slow-moving run, collect 5 kicknet samples and 3 core samples).
 - d. Targeted habitat types in order of sampling preference (see Definitions, Section 2.4; Figure 14):
 - i. Riffles: Surber (SOP C.1) or Hess (SOP C.7)
 - ii. Runs: Surber (SOP C.1), Hess (SOP C.7), or modified kicknet (SOP C.6)
 - iii. Snags: D-frame snag net (SOP C.3)
 - iv. Pools: hand corer (SOP C.4) or Hess (SOP C.7)
3. Start sampling at the bottom of the reach, working upstream so as not to stir up sediments in the water column which can decrease visibility and cause invertebrates to drift.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

4. Spread samples out along the reach. For example, do not collect all samples for the same substratum in the same riffle, collect samples from 5 different riffles along the reach.
5. Do not sample anywhere you or other field people/animals have walked in the reach, or locations that appear recently disturbed (e.g., overturned rocks, footprints, dislodged plants, other evidence of wildlife, cattle, humans, etc.).




Figure 14. Wadeable stream decision tree for choosing the appropriate sampler.

SOP C Field Sampling

C.1 Surber Sampler



In **wadeable streams**, the Surber sampler is used in shallow riffle and run habitats.

1. Ensure that all samples are collected from riffles of similar depth and flow (within approximately 20%) in the **wadeable stream**. Ensure that water level is below the top of the Surber frame (best practice for sampling using a Surber).
2. Choose a location in the riffle that has flowing water and appears to be underwater most of the time (i.e., not underwater only at high flow). Avoid locations that are on top of, or just downstream of, large boulders (e.g., boulders that affect the flow of water at your location). Ensure that all substrata within the Surber frame are underwater.
3. Set up the Surber sampler by extending the base and clipping the arms into the screws on the base of the Surber frame (Figure 15).
4. Carry the 3 gallon bucket and Surber sampler with you to the sample location in the stream.
5. Approach sample location from downstream so as not to step on the cobbles that you want to sample.
6. Fill 3 gallon bucket $\frac{1}{4}$ - $\frac{1}{2}$ full with stream water so that it is weighted when resting on the stream bottom or manually hold bucket in place. Place the bucket on the stream bottom in a shallow part of the riffle (or on the shore) **that you can still reach** from the Surber location.
7. Orient the Surber so the opening of the net is facing into the stream flow (Figure 15).




Figure 15. Diagram of Surber sampler set-up. The inside of the base is the sample area of the stream bottom (0.09 m²).

8. Place the **back edge of the frame on the stream bottom first** so that any material dislodged will flow into the net. Gently lower the rest of the base onto the substratum. Once base is placed on the stream bottom, do not move the sampler.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

- a. Note the dominant substratum size class at the sampling location in the mobile app.
 - b. Always stand downstream of the frame so you do not kick additional material into the sample.
 - c. Hold Surber in place using hand or brace against your leg or knee. Avoid stepping on the bottom frame as that can affect the flow of water into the net.
 - d. Ensure that nothing obstructs the flow of water into and out of the net (i.e., the net should not be kinked or partially out of the water).
9. Remove cobbles one at a time from the area inside the base of the Surber frame (Figure 15).
- a. Hold each cobble near the net opening and lightly brush debris, insects, etc. from all surfaces of the cobble with your hands. The stream flow will rinse this material into the Surber net.
 - b. Place cobbles in 3 gallon bucket (Figure 16).
 - c. Continue until the top layer of cobbles has been removed from the net.
 - d. For cobbles that are partially inside and outside of the frame: for every 1 cobble that you select that is partially outside of the frame, leave one cobble that is partially outside of the frame in the substratum (Figure 17).



Figure 16. Hold the Surber net on the stream bottom, and keeps the bucket nearby for depositing rocks from the base of the Surber.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C




Figure 17. Cobble selection at Surber edges. The yellow square represents the bottom of the Surber sampler.

10. After the top layer of cobbles has been removed and placed in the bucket, disturb the remaining sediments (~10 cm deep; Cuffney et al. 1993) with your hand or kitchen brush so that all detritus flows into the Surber net for 1 minute.
11. After all suspended material has been washed into the net, lift the Surber sampler up off the substratum.
12. Dip the net into the stream a few times to rinse the sides of the net, always directing flow towards the back of the net. This allows material caught in the net to concentrate at the bottom of the net. Be sure to keep the net opening above the water surface so as not to accidentally lose or collect additional material in the sample.
13. Return to the processing location on the stream bank with the bucket of cobbles and the Surber sampler.
14. Set the Surber at the side of the stream so that the frame is on shore, and the end of the net (and all material collected) is sitting in water (to keep insects alive).
15. Scrub each cobble in the bucket using the kitchen brush. Scrape off all aquatic plants using the pot scrubber side of the nylon kitchen brush or a putty knife. Brush all invertebrates into the bucket (Figure 18).
 - a. Scrub gently but firmly to remove insects, but not so vigorously as to damage insects. They are often identified by fragile anatomical structures such as external gills.
 - b. Rinse the cobble in the bucket. Visually inspect the cobble for organic material (e.g., moss) and clinging invertebrates (e.g., caddisflies and snails) before discarding.
 - c. Discard cleaned cobble onto the stream bank.
 - d. Repeat until all cobbles in the bucket have been scrubbed and discarded.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 18. Scrub rocks from the Surber sample in the 3 gallon bucket

16. Invert Surber net (turn it inside-out) into bucket of water. Swirl net around in bucket water to remove all material from the net. Use your hands to brush material from the net into the bucket.



- a. Immediately release any fish or other vertebrates captured in the net. You may write a remark in the mobile app if you know what species was released.
- b. Depending on site-specific permits, mussels collected in the sampler may also need to be released. Make a remark in the data collection app if this occurs, and the species or common name if you know the type(s) of mussels collected.
- c. Use 500 mL wash bottle filled with stream water to rinse any residual organic matter or insects from the net (Figure 19). Check for clinging insects.



Figure 19. Removing the tip of the 500 mL wash bottle helps makes rinsing easier and increases water pressure. This tip pulls easily out of the main body of the wash bottle.

17. Once the Surber net is empty, all of the sample material will be suspended in water in the 3 gallon bucket. Proceed to Section C.9: Sample Elutriation and Preservation.
18. After elutriation and preservation, move to next location and repeat the above steps until you have the desired number of samples.
 - a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat.

C.2 Petite Ponar



The petite ponar is primarily used for benthic sampling in **lakes** and **rivers**. In **wadeable streams**, the petite ponar may be used in pools with soft sediments that are too deep to use the hand corer safely.

1. Navigate to sampling location:
 - a. For **wadeable streams**; sample in pools of similar depth and flow that have soft substratum, and are > 1 m deep.
 - a. 5 locations for dominant habitat, 3 locations for secondary habitat.
 - b. For **lake and river** sample in three locations:
 - i. **Lakes** (near water chemistry sampling locations):
 - 1) Deepest point in the lake, determined by bathymetric site map and GPS coordinates (location = c0)
 - 2) Near the lake inlet (location = in)
 - 3) Near the lake outlet (location = ot)
 - a. **Rivers** (near water chemistry sampling location and 2 other haphazardly chosen locations):
 - 1) Sensor/buoy location (location = c0)
 - 2) Choose two other locations representative of the sensor location. Locations should be ± 10 m of the river depth at the buoy and a minimum of 50 m apart from each other.
2. In **wadeable streams** stand just downstream of the location or on the bank near where you want to sample. Do not disturb the sediments where you plan to sample.
 - a. Note the dominant substratum size class at the sampling location in the mobile app.
3. In **lakes and rivers**, gently lower an anchor at the bow and allow boat to float back with wind or current to sampling location. Drop a second anchor at the stern to hold boat in place.
 - a. Allow ~5 minutes for sediments to settle after lowering the anchor, you can use this time to prepare the sampling equipment.
 - b. Using a bow anchor rope 2 times the water depth will minimize disturbance of the sediment at the sampling location.
 - c. Sample on the side of the boat, away from the motor and anchor, so as not to interfere with the ponar or disturb the sediments
4. Release the safety pin on the ponar sampler and open the bottom of the ponar (Figure 20). Place the pinch-pin (with spring) in the ponar and hold the ponar by the rope at the top. The sampler should



stay in the open position as long as there is tension on the rope. The ponar will close automatically when the tension is released (i.e., the sampler hits sediment).




Figure 20. Example of a petite ponar setup

5. Hold the open ponar above the water surface above the point where you want to sample.
6. Slowly lower the ponar in the water and maintain rope tension.
7. When the ponar hits the sediments and the lines goes slack, pull up on the rope to close the jaws.
8. If the jaws do not close when the sampler hits the **lake/river** bottom, attach a messenger to the line and drop onto the ponar to trigger the jaws to close.
9. Pull the ponar up to the surface using the rope.
10. Check to see if the ponar properly closed. If it did not close or there is an object (such as a stick) holding the jaws open, dump the sample away from your next sampling location and return to Step 5 in a different location (at least 2 m away from original location in lakes and rivers).
11. If the ponar is properly closed, place the sampler over the bucket and open the jaws to release the sample.
 - a. NOTE: Ponar sampling in areas of heavy macrophyte growth may cause the ponar to close improperly. Sample in areas of lighter or no plant growth if possible.
12. Rinse the inside of the ponar into the bucket using the 500 mL wash bottle.
 - a. If in a **lake**, rinse the inside of the ponar into the bucket using the 500 mL wash bottle filled with filtered (through the 250 μ m sieve) **lake** water to exclude zooplankton.
 - b. If in a **river** and zooplankton is apparent in rinsewater to the naked eye, use 250 μ m filtered water as detailed in the previous step.
13. Once ponar is empty and clean, all of your sample material will be in the 3 gallon bucket.
14. Carefully add water to the bucket to until bucket is about $\frac{1}{2}$ full.
 - a. In a **lake**, use >250 μ m filtered water to remove zooplankton. You may either use the 250 μ m sieve or 243 μ m Nitex mesh (used for preservative change in lab) to filter water.
15. Proceed to Section C.9 Sample Elutriation and Preservation.
16. After elutriation and preservation, rinse sampler with native water, move to the next sampling location and repeat the steps above until you have the desired number of samples.



Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat
- b. **Lakes and rivers:** 3 samples

C.3 Woody Snag Sampling (small woody debris)



1. Woody snag sampling should be used where snag/woody debris fits inside a D-frame net for sampling. This method is considered quantitative because all of the sample material fits inside the net. Sample in areas of similar flow and depth for each sample.
 - a. Snags must be submerged and appear to be underwater most of the time (i.e., not underwater only at high flow).
 - b. Snags must account for >20% of habitat throughout the sampling area.
 - c. Snags may include leaf litter packs, overhanging branches, submerged wood (< 0.3 m (6 inches) in diameter and < 5 m long. If using leaf litter packs/debris must be present throughout the year (not just seasonally).
 - d. Note the dominant substratum size class below the snag at the sampling location in the mobile app.



Figure 21. Sites such as D08 Mayfield Creek are well-suited to snag sampling with their sandy/silty substrate and abundance submerged large woody debris.

2. Two people are needed to collect the sample. Place the 243 μ m mesh bag (D-frame net) around the end of the snag with the bag opening facing upstream so invertebrates will not escape.
 - a. If there is slow- or no flow at the sampling location, try to angle the net toward the water surface to prevent macroinvertebrates from swimming away.
3. The second person should quickly saw or lop the snag near the end of the sampling net (near the mouth of the D-frame net).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

4. Remove the snag section covered by the bag by sawing with the bow saw or breaking the snag at the end of the bag.
 - a. If you are unable to remove the snag or need to leave it in the stream for other sampling, you may scrub into the net without breaking off the piece as long as the stream flows into the net to collect any organisms that are brushed off the snag. This step requires flow to be present at the sampling location.
5. Fill 3 or 5 gallon bucket $\frac{1}{4}$ - $\frac{1}{2}$ full with native water.
6. **Wadeable stream:** Remove snag from net and place in the bucket of stream water.
7. Invert net (turn it inside-out) into the bucket of water. Swirl net around in bucket water to remove all material from the net. Use your hands to brush material from the net into the bucket.
8. Use the 500 mL wash bottle filled with native water to rinse any residual organic matter or insects from the net. Check for organisms clinging to the sides of the net or in the seams.
9. **Wadeable stream:** Brush insects off snag surface using the nylon kitchen brush.
 - a. Rinse snag surface into bucket using the 500 mL wash bottle.
 - b. Measure length and width of snag and record in the mobile app.
 - c. Visually inspect snag and remove any remaining insects using flexible forceps or disposable pipet.
10. All sample material should now be in the 3 or 5 gallon bucket.
11. Fill out the mobile app with location, date, and type of samples **Error! Reference source not found..**
12. Proceed to Section C.9 Sample Elutriation and Preservation.
13. After elutriation and preservation, rinse net in stream, move to next sampling location and repeat the steps above until you have the desired number of samples
 - a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat



C.4 Large Woody Debris Sampling

Large woody debris (LWD) sampling is intended for logs that are too large to cut off and sample via the snag method (SOP C.3). This sampling method is considered semi-quantitative because the entire substrate that is sampled does not fit inside the net.

1. Sample in areas of similar flow for each sample.
 - a. LWD must be submerged and appear to be underwater most of the time (i.e., not underwater only at high flow).
 - b. LWD must account for >20% of habitat throughout the sampling area.
 - c. LWD is typically characterized by trees that have fallen into the stream/river from the bank, or have been carried downstream by the current and become lodged against the stream/river bottom.
 - d. In a river, choose either 5-even or 5-odd riparian sections for sampling

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- a. Choose sections by looking at the time: if the minute is even, sample even sections. If the minute is odd, sample odd sections.
 - b. If there is no LWD in the section chosen, proceed to the next section. You may sample 2 snags from the same section if necessary, as long as they are >5 m apart.
 - c. The sample number on the sample labels should correspond to the Riparian Habitat Section numbers.
 - e. Note the dominant substratum size class below the snag at the sampling location in the mobile app.
2. Ensure that the LWD is submerged to at least 0.6 m (2 ft) deep, in flowing water (**river** only), and has a diameter of ≥ 0.15 m (6 inches). The snag should either break the water surface or come within 0.3 m (1 ft) of the water surface for ease of sampling (Angradi et al. 2006).
- a. Navigate boat to first LWD, approaching slowly from downstream.
 - b. Carefully drop and anchor the boat or have the boat driver should hold the boat in place in the current using the boat motor.
 - c. Place the modified kick-net (13" x 20" opening) on top of the LWD with the opening facing up-current, just below where the snag breaks the water surface. Make sure the frame of the net is touching the LWD surface
 - d. Using the long-handled deck brush, scrub ~1 m of snag so that organisms and debris wash into the sampling net (Figure 22). Scrub the top and sides of the snag.
 - a. As this is a semi-quantitative method, not all organisms will be washed into the net.
 - e. The length is assumed to be 1 m and the width is assumed to be the width of the modified kicknet, you do not need to record length or width.
 - f. At the end of the sweep, turn the net opening toward the water surface and lift out of the water to prevent organisms from escaping.
 - g. Dip net into the water a few times to rinse the sides of the net, always directing flow towards the back of the net. This allows material to concentrate at the bottom of the net. Be sure to keep the net opening above the water surface so as not to accidentally lose or collect additional material in the sample.
 - h. Pull the net into the boat.



Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 22. From Angradi et al. 2006, example of snag sampling in a large river. While the boat driver holds the boat in position, one person holds the modified kicknet against the snag, while a second scrubs the snag with a long-handled deck brush.

3. Fill 3 or 5 gallon bucket $\frac{1}{4}$ - $\frac{1}{2}$ full with native water.
4. Invert net (turn it inside-out) into the bucket of water. Swirl net around in bucket water to remove all material from the net. Use your hands to brush material from the net into the bucket.
5. Use the 500 mL wash bottle filled with native water to rinse any residual organic matter or insects from the net. Check for organisms clinging to the sides of the net or in the seams.
6. All sample material should now be in the 3 or 5 gallon bucket.
7. Fill out the mobile app with location, date, and type of samples **Error! Reference source not found.**
8. Proceed to Section C.9 Sample Elutriation and Preservation.
9. After elutriation and preservation, rinse net in stream, move to next sampling location and repeat the steps above until you have the desired number of samples
 - a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat
 - b. **River:** 5 samples

C.5 Hand Corer



The hand corer is used in **wadeable streams** in pools or runs with sand or silt substrata.

1. Sample in areas of similar flow and depth along the **wadeable stream** sample reach.
 - a. Sample only soft sediments (sand, silt, clay).
2. Rinse the corer assembly to be sure that all screw threads are clean of silt and sediment.
3. Assemble the hand corer (Figure 23).



- a. Screw the corer head onto the top of the stainless steel core tube (Figure 23). **NOTE:** Petroleum jelly may be applied to the threads to aid sealing.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- b. Cores are usually more stable without the PVC liner tube. The corer may be used with or without the liner tube and core catcher, this decision may be made by the field ecologist at the time of sampling.
- c. Screw the stainless steel nosepiece onto the bottom of the core tube (Figure 23).
- d. Petroleum jelly may be applied to the flutter valve to help create suction in the corer.




Figure 23. Hand-corer assembly: A) Disassembled corer. Use of the liner tube and core catcher are optional. B) Assembled corer. Note: the nosepiece may be stainless steel (not black Lexan as in photo) in some domains

4. Approach sample location from downstream so as not to step in the location where you want to sample.
5. Hold the core sampler firmly by the handle (Figure 23).
6. Push the core sampler through the water and into the sediments in one smooth, continuous movement (Figure 24). Allow the flutter valve to remain open.
 - a. Depending on the sediment type, it may take a lot of force to push the corer into the sediments.
 - b. Do not hammer or pound the corer into the sediments.
 - c. Keep barrel of corer at a 90° angle with the sediments.
 - d. Note the dominant substratum size class at the sampling location in the mobile app.



Figure 24. Push the hand corer through the water and into the sediments at a 90° angle

7. Push corer approximately 5-10 cm into the substratum while keeping the blue flutter valve open.
 - a. Pre-measure 5 cm and 10 cm on the outside of the corer before sampling.
8. If the corer is not completely submerged, wet the blue flutter valve (or apply petroleum jelly) on the top of the corer head and close by hand (Figure 23).
 - a. The valve must be kept wet to maintain a good seal and prevent loss of sample when the corer is extracted. Petroleum jelly may help keep the flutter valve sealed.
 - b. If the corer is submerged, allow air to escape from the flutter valve. When the corer is pulled up, the flutter valve should close by itself.
9. Holding the flutter valve closed, **slowly** pull the corer straight up and out of the sediments.
 - a. If the corer is pulled up too fast, you may lose the contents.
 - b. You may also use a spatula or your hand to cap the bottom of the core before pulling it out of the sediments if maintaining suction is a problem at the site
10. Continue to hold the flutter valve closed and lift the entire core sampler clear of the water, keeping the corer vertical so as not to spill the sample.
 - a. If the sample spills before reaching the bucket, you may rinse the corer and start over at Step 3 approximately 0.5 m away from the original location, as long as it has not been disturbed.
 - b. If some, but not all, of the sample spills and is not deposited in the bucket, discard the entire sample and start over.
 - i. Use a secondary container to deposit each core so that if one core fails, the entire composite sample is not lost.
11. Quickly hold the core sampler over the 3 gallon bucket and release the flutter valve, allowing the sample to drop into the bucket.

- a. Depending on suction in the corer, the sample may drop into the bucket soon after it is removed from the water.



12. Fill the 500 mL wash bottle with stream water and rinse any residual organic matter or insects from inside the corer into the bucket.

- a. Check for clinging insects.

13. Once the corer is empty, all of your sample material will be suspended in water in the 3 gallon bucket.

14. Repeat Steps 3-13 two more times, until there is a composite of 3 cores in the 3 gallon bucket. Proceed to Section C.9 Sample Elutriation and Preservation.

- a. 3 cores = 1 composite sample

15. After elutriation and preservation, clean corer in stream water and move to next location and repeat the steps above until you have the desired number of composite samples.

- a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat

C.6 Modified Kicknet Sampler



The modified kicknet may be used for deep runs in **wadeable streams**, or benthic sampling in **rivers** with cobble or bedrock substrata in place of the petite ponar.

1. Choose runs (or deep riffles) that are similar in flow and depth.
2. Make sure net is firmly attached to handle.




Figure 25. Example of modified kicknet setup.

3. Approach sample location from downstream so as not to disturb the location where you want to sample.
4. Orient the net so the opening of the net is facing into the stream flow.
5. Place the bottom edge of the frame on the stream bottom first, hold in place. Once the net edge is placed on the stream bottom, do not move the net (Figure 25).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

6. Disturb the substrata ~0.25 m² upstream of the kicknet.
 - a. **Wadeable stream:** Place 0.25 m² quadrat just upstream (1-5 cm) of the kicknet edge.
 - a. If you can reach the stream bottom of the wadeable stream with your hands, pick up each cobble and brush the surface with a kitchen brush so that the stream current carries all insects/organic matter into the net.
 - 1) For cobbles that are partially inside and outside of the frame: for every 1 cobble that you select that is partially outside of the frame, leave one cobble that is partially outside of the frame in the substratum (Figure 25).
 - 2) Once a cobble is cleaned, discard to the side or downstream of the sample area. Do not resample cobbles.
 - ii. If you cannot reach the stream bottom, step into the quadrat. Use feet to disturb the sediments by kicking back and forth for 60 seconds inside the quadrat, so all organic matter flows into the net.
 - b. **Rivers:** If water is too deep for wading, disturb substrata using a long-handled brush so all organic matter flows into the net and estimate the area of the 0.25 m² quadrat.
7. Sweep the kicknet toward the water surface, taking care to keep the opening facing upstream so no contents will spill.
8. Dip the net into the stream a few times to rinse the sides of the net, always directing flow towards the back of the net. This allows material caught in the net to concentrate at the bottom of the net. Be sure to keep the net opening above the water surface so as not to accidentally lose or collect additional material in the sample.
9. Take the net to a processing location on the stream bank.
10. Note the dominant substratum size class at the sampling location in the mobile app.
11. Half-fill 3 or 5 gallon bucket with native water.
12. Invert net (turn it inside-out) into bucket of water. Swirl net around in bucket water to remove all material from the net. Use your hands to brush material from the net into the bucket.
-  13. Use 500 mL wash bottle to rinse any residual organic matter or insects from the net.
 - a. Check for clinging insects.
14. Once the net is empty, all of the sample material will be suspended in water in the 3-5 gallon bucket. Proceed to Section C.9 Sample Elutriation and Preservation.
15. After elutriation and preservation, clean net in stream water and move to next location and repeat the steps above until you have the desired number of samples.
 - a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat
 - b. **River:** 3 samples (replaces petite ponar samples)

C.7 Hess Sampler



In **wadeable streams**, the Hess sampler should be used in shallow riffles, runs or pools where the other samplers above will not work due substratum type or stream flow.

1. Ensure that all samples are collected from areas of similar depth and flow (within approximately 20%). Water level must be below the top of the Hess frame.
2. Choose a location that appears to be underwater most of the time (i.e., not underwater only at high flow). Avoid locations that are on top of, or just downstream of, large boulders (e.g., boulders that affect the flow of water at your location).
3. Carry the 3 gallon bucket and Hess sampler with you to the sample location.
4. Fill 3 gallon bucket $\frac{1}{4}$ - $\frac{1}{2}$ full with stream water so that it is weighted when resting on the stream bottom or manually hold bucket in place. Place the bucket on the stream bottom in a shallow part of the riffle (or on the shore) **that you can still reach** from the sampling location.
5. Position the Hess frame securely on the stream bottom, with the screened opening facing upstream and the net facing downstream (Figure 26)
 - a. Hold the sampler in position by applying pressure with your knees to the back of the sampler, or have a second person hold the sampler.
 - b. Note the dominant substratum size class at the sampling location in the mobile app.



Figure 26. Hess sampler with collection net and dolphin bucket

6. Reach into the sampler and remove any large substrata (i.e., cobbles) and place in the 3 gallon bucket.
7. After the top layer of cobbles has been removed and placed in the bucket, disturb the remaining sediments (~10 cm deep; Cuffney et al. 1993) with your hand or kitchen brush so that all detritus flows into the Hess net (typically ~30-60 seconds).
 - a. If there is insufficient stream flow to wash sample and detritus into the net, create flow with your hands until the water inside the Hess sampler appears clear.
8. Dip the net into the stream a few times to rinse the sides of the net, always directing flow towards the back of the net and dolphin bucket. This allows material caught in the net to concentrate at the bottom of the net. Be sure to keep the net opening above the water surface so as not to accidentally lose or collect additional material in the sample.
9. Return to the processing location on the stream bank with the bucket of rocks and the Hess sampler.
10. Set the Hess at the side of the stream so that the frame is on shore, and the end of the net (and all material collected) is sitting in water (to keep insects alive).
11. Scrub each cobble in the bucket using the kitchen brush. Scrape off all aquatic plants using the pot scrubber side of the brush. Brush all invertebrates into the bucket.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- a. Scrub gently but firmly to remove insects, but not so vigorously as to damage insects. They are often identified by fragile anatomical structures such as external gills.
-  b. Rinse the cobble in the bucket. Visually inspect the cobble for organic material (e.g., moss) and clinging insects (e.g., caddisflies) before discarding.
- c. Discard cleaned cobbles on the stream bank.
- d. Repeat until all cobbles in the bucket have been scrubbed and discarded.

12. Rinse all material in the net into the dolphin bucket.
13. Holding the end of the net and dolphin bucket over the 3 gallon bucket, unscrew the dolphin bucket and rinse its contents into the 3 gallon bucket.
 - a. Invert net into 3 gallon bucket and rinse any remaining insects to the sample.
14. Once the Hess net is empty, all of the sample material will be suspended in water in the 3 gallon bucket. Proceed to Section C.9: Sample Elutriation and Preservation.
15. After elutriation and preservation, clean net in stream water and move to the next location and repeat Steps 5-14 until you have the desired number of samples
 - a. **Wadeable streams:** 5 samples for the dominant habitat type, 3 samples for the secondary habitat

C.8 D-net Measured Sweep Samples (Semi-quantitative)



In lakes and rivers, the D-net sweep samples are the preferred sampling method for littoral samples.

1. Sampling locations will correspond to the 10 habitat stations set forth in the Riparian Habitat Assessment Protocol (RD[15]). This divides the lake/river margins into 10 sections (Figure 27).




Figure 27. Example of Riparian Stations splitting the lake into sections at D04 Lake Barco.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

2. Choose either the 5-even or 5-odd habitat sections for sampling.
 - a. Choose sections by looking at the time. If the minute is even, sample even sections. If the minute is odd, sample odd sections.
 - b. The sample number on the sample labels should correspond to the Riparian Habitat Section numbers.
 - c. Sample in rooted plant habitat <1m deep if possible. Choose similar depth and habitat to sample in each section.
 - i. If the lake has no rooted plant habitat, sample floating vegetation mats.
 - ii. Senescent or dead plant material is acceptable for sampling.
 - d. You may sample anywhere along the shoreline of the section in order to find the preferred sampling habitat. If no preferred habitat is available, skip to the next section, then continue with the previously selected sections.
3. Navigate boat to an aquatic plant bed in the chosen sampling section. Ensure that you are able to reach the lake/river bottom with the sampling net.
4. If permits allow and the area of the lake or river is shallow enough to wade, step out of the boat and sample by wading (permits will be provided by NEON Permitting). If permits are not available, sample near the bow of the boat, away from the motor so the motor will not interfere with the sweep net or disturb the sediments.
5. Attach handle to D-frame net (Figure 28).



Figure 28. D-frame net, used for sweep samples in vegetation and silty habitats.

6. Sweep the D-frame net through the vegetation across a 1 m distance (DiFranco 2006, USEPA 2011).
 - a. To determine the sweep length, measure 1 m on the net handle (typically 1 m = the wooden part of the handle). Using this as a reference, place feet 1 m apart on the lake/river bottom and sweep from foot to foot

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- b. The net should remain submerged during the entire sweep, and the bottom of the net should brush the sediments during the entire sweep (Figure 29).
- c. For rooted aquatic plants: bump or jab the bottom of net frame against the sediment several times (> 3 times) to collect benthic organisms while keeping the net frame close to, but not scraping, the bottom.
- d. For floating vegetation mats: scoop all vegetation into the net.
- e. Keep net in motion to prevent organisms from swimming out of the net. Conduct sweep quickly, entire sweep should last ~3 seconds.
- f. At the end of the sweep, turn the net opening toward the water surface and lift out of the water to prevent organisms from escaping.
- g. Retain all plants that are completely in the net in the sample. If plants are hanging on the net frame, break the plants and include the portions that are in the net with the sample, discard those that are hanging outside the net.
- h. Rinse net by dipping in the water, keeping the mouth of the net above the water line so as not to introduce additional organisms to the sample.



Figure 29. D-frame sweep technique in a littoral area; the D-frame net must remain submerged and close to the substrate throughout the entire sweep.

7. For floating aquatic plants only, hold the net in the water with the mouth above the water line. Agitate the plant material with your hands, in water in the net for 1 minute. Rinse plant material with 500 mL wash bottle if necessary. Inspect vegetation to ensure that you have removed invertebrates. Remove and discard plant material while keeping macroinvertebrate sample in the net (FDEP 2011).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

a. Keep in mind that this is a quantitative sampling approach, so do not discard material that contains macroinvertebrates.

8. With the macroinvertebrate sample in the net, dip D-frame net into the water a few times to rinse the sides of the net, always directing flow towards the back of the net. This allows material to concentrate at the bottom of the net. **Be sure to keep the net opening above the water surface** so as not to accidentally lose or collect additional material in the sample.



9. Pull the net into the boat.

10. Fill the 3 gallon bucket $\frac{1}{4}$ – $\frac{1}{2}$ full with 250 μm filtered **lake** water to exclude most zooplankton.

11. Invert net (turn it inside-out) into bucket of filtered rinsewater. Swirl net around in rinsewater to remove all material from the net. Use your hands to brush material from the net into the bucket.



12. Use 500 mL wash bottle filled with 250 μm filtered **lake** water to rinse any residual organic matter, plants, or organisms from the net into the bucket. Check for organisms clinging to the sides of the net or in the seams.

a. All sample material should now be in the 3 or 5 gallon bucket.

13. Fill out field mobile application and label with location, date, and type of sample (**Error! Reference source not found.**).

14. Complete Sample Elutriation and Preservation (SOP C.9).

15. After elutriation and preservation, rinse net in native water and move to the next location, repeating the steps above until you have the desired number of samples.

a. **Lakes and rivers:** 5 samples

C.9 Sample Elutriation and Preservation

1. Samples only need to be elutriated if they have inorganic material that you do not want to include with the sample. If the sample is all organic material, include all material in the sample and proceed to preservation (Step 15).

2. Gently swirl contents in bucket to create a “whirlpool” and suspend organic material. This process is called elutriation (Figure 30).

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C



Figure 30. Process of elutriation (Dates and Byrne 1997).

3. Carefully pour contents of bucket into 250 μm sieve or sieve bucket (Figure 31). If you are in a boat, hold the sieve over a 5 gallon bucket to capture the waste water. Some material will be retained in the original bucket.
 - a. The sieve bucket should be used for petite ponar samples for thick, fine sediments.
 - b. If the sieve fills up with organic matter, you may pick clumps out of the sieve and place in sample jar.
 - c. You may use your fingers or shake the sieve or sieve bucket to stir the sample and move fine material through the sieve.
 - d. You may use low-pressure water to wash sediment through sieve mesh. High pressure will damage organisms.
 - e. Sieving the sample in small portions may help prevent clogging.
 - f. Continue rinsing to reduce the sediment in the sample, especially for petite ponar samples. Reduce samples to ≤ 750 mL if possible.



Figure 31. Carefully pours water from the 3 gallon bucket into the sieve.

4. Partially refill bucket with water (bucket opening should be facing upstream) without losing any of the organic matter contents of the bucket.
 - a. Use 250 μm filtered water in lakes to exclude zooplankton. You may use the 250 μm sieve or 243 μm Nitex mesh (used to change preservative in the lab) for filtering rinsewater.
5. Repeat elutriation (Steps 2-4) until the water appears relatively clean. There may be some sand or silt in the bottom of the bucket. Elutriate a **minimum** of 3 times per sample.
 - a. Elutriating ~3-5 times (until you no longer see insects in the swirled water in the bucket) is typically sufficient to remove insects from the inorganic matter.
 - b. At sites with fine sediments (i.e., petite ponar samples in lakes), elutriation may be particularly difficult. If the sieve bucket, dunk the bottom of the sieve bucket directly into the lake water, without adding new water to the top of the bucket, to facilitate sediment rinsing.
6. Check sides of bucket for clinging invertebrates. Check sand/inorganic material at the bottom of the bucket for caddisflies (rock cases) or other heavy invertebrates (e.g., snails), place in sample container using forceps or fingers. Retain any plant material in the sample jar.
 - a. Place any invertebrates from this inspection in the sieve with the rest of the sample.
 - b. Mussels may need to be returned to the stream depending on permitting requirements.
7. Discard inorganic material remaining in the bucket, and rinse bucket with native water. Set bucket aside.
8. The entire sample should now be in the sieve or sieve bucket.
9. Add a waterproof paper label (write in pencil) inside the sample jar **AND** a small adhesive label and/or barcode label (if available) to the outside of the sample jar with the sample ID for use by the



Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

external taxonomy lab. Write in pencil as ethanol will erase permanent marker. Make sure the label sample ID matches the sample ID generated by the data ingest.

- a. Sample ID format: *SITE.DATE.sampleType.sampleNumber* (
 - b. Table 8)
 - c. Example: *ARIK.20140620.kicknet.3*
10. Fill the 500 mL wash bottle with native water. Use 250 µm filtered water in lakes to exclude additional floating invertebrates.
 11. Rinse sieve screen and edges with wash bottle and tap sieve until organic material is collected at one edge of the sieve (Figure 32).



Figure 32. Rinse the sample from the sieve into the open container with the 500 mL wash bottle.

12. Open the sample jar and carefully rinse (using the 500 mL wash bottle) sample from the sieve into the sample jar. You can also use your fingers to move the sample from the sieve into the sample jar.
 - a. Use as little water as possible. Be sure to rinse sieve and fingers into the sample jar to thoroughly remove all material.
 - b. If there is too much rinse-water, you may re-sieve sample by dumping contents of sample jar back into the sieve, and repeating Steps 11-12.
13. If sample is too large for one sample jar, you may use multiple jars. Each jar must be properly labeled with site and date information, as well as “Sample 1 of 2” or “Sample 2 of 2”.
 - a. If available, use a barcode label on sample jar 1 and band or tape the two jars together
14. Check sieve for clinging insects that may not have been washed into the sample jar.
15. **Carefully** add preservative. Preserving immediately prevents damage to insects in the samples.
 - a. Wear latex gloves when preserving samples.



Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- b. Preserve samples in a well-ventilated location (e.g., outdoors).
 - c. Add enough ethanol preservative to the sample to preserve in a 1:1 sample material: preservative ratio (sample material includes water in the jar). Ideal preservation is 70% ethanol, but using 1:1 as an eyeball estimate is usually a good start for the field preservation.
16. Record data in the mobile app.
- a. If available, scan the barcode label with the tablet (Figure 33).
 - b. Record all relevant metadata for each sample in the mobile app.
 - c. Ensure that the human-readable sample ID matches the sample ID generated by the mobile app.




Figure 33. Barcode label scanning.

17. Close the sample jar tightly.

C.10 Sample Preservation

Preserve samples using 95% ethanol streamside/lakeside or at the field vehicle (see details above in each sampling section) to prevent predation within the samples to a final concentration of ~70% ethanol.

C.11 Ending the Sampling Day

1. Refresh the sampling kit
 - a. Replace sample jars and resealable bags.
 - b. Print new field labels and field data sheets. Make sure barcode labels are available.
 - c. Refill/restock preservative containers.
2. Equipment maintenance, cleaning and storage
 - a. Decontaminate all equipment that has come in contact with site water according to the NEON Aquatic Decontamination Protocol (RD[08]).
 - b. Dry all equipment thoroughly between sites and before storage.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

- c. Check all nets for holes and patch if necessary.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

SOP D Macroinvertebrate DNA Metabarcoding Field Collection

Macroinvertebrate DNA samples are collected during each sampling bout, three times per year. Samples collected specifically for DNA metabarcoding will be analogs to three of the samples already being collected in the dominant habitat type for morphological taxonomy. This sampling approach uses the community metabarcoding approach, where replicate samples from the site are preserved in high-concentration ethanol for sequencing analysis.

D.1 Sterilize equipment

All equipment must be cleaned and sterilized prior to sample collection at the site to prevent contamination of DNA from the person collecting the sample, DNA from another site, or DNA from the environment outside of the site (Laramie et al. 2015).

1. Cleaning equipment:
 - a. Wearing nitrile gloves, clean all nets, waders, and other equipment that comes in contact with samples during macroinvertebrate sampling using a 10% bleach solution. Follow with a DI rinse to remove the residual bleach (Jane et al. 2014). Note that this is a higher concentration that is usually used in the Aquatic Decontamination Protocol (RD[08]).
 - i. Equipment to decontaminate with stronger solution:
 1. Sampling net(s)
 2. Sieve
 3. Bucket
 4. Brush
 5. Boots/waders
 6. Sample jars if they are being reused from other sampling, or come uncapped from the manufacturer
2. Wearing clean nitrile gloves, place equipment and consumables in a clean bag so as not to contaminate it on the way to the field site.

D.2 Field collection

1. Fill out and place an adhesive label on the sample jar. Circle “DNA” on label. **Do not** use a paper label inside the sample jar for this protocol. If available, add an adhesive barcode label.
2. Collect an additional sample at 3 of the 5 dominant habitat sampling locations chosen above (SOP B). Use the same sampler already chosen to use for taxonomy samples at each of those locations.
 - a. Choose 3 riparian sections or habitat units that 1) have enough habitat to support two samples and 2) are spread out along the stream/river reach or lakeshore (ideally samples 1, 3, and 5).
3. Prior to sampling, prime the sampler by rinsing well with local source water.
4. Collect samples according to SOP B for the appropriate habitat type and sampler.
5. Choose “DNA” in the mobile app, and the appropriate habitat and sampler metadata.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

6. Sample ID = *SITE.YYYYMMDD.sampleType.sampleNumber.DNA*
7. After sample collection, use forceps or clean-gloved hands to pick out large organic matter, leaving the macroinvertebrates in the sample.
8. After the entire sample is in the sample jar, carefully drain the some of the extra water off the top. You may want to use the sieve to help drain without losing macroinvertebrates from the sample.
9. Add 95% ETOH to sample jar to completely cover sample (Stein et al. 2012). ETOH concentration should be as close to 95% as you can get (as little extra water as possible).
10. Return sample to domain lab and store in the dark at 4 °C and proceed to Section E.3.

SOP E Laboratory Sampling and Analysis

E.1 Preparation

1. Fill 500 mL wash bottle with 475 mL 95% undenatured ethanol and 25 mL 99% glycerol (final concentration: 5% glycerol; Stein et al. 2013). Clearly label bottle.

E.2 Processing Samples – Taxonomy

1. Replace preservative between 24 and 72 hours of field collection in the domain lab.
2. Wearing safety glasses and nitrile gloves, open field-preserved sample under fume hood.
3. Carefully decant liquid over a clean 250 µm sieve or filter cup similar to that used in the TOS Beetle Protocol (RD[10]) over an ETOH waste container. Take care not to lose any sample material.
 - a. Rinse down sides of sample jar with ETOH/glycerol wash bottle so no material remains near the top of the sample jar.
 - b. If using sieve, check for any macroinvertebrates or other organic material that may have come from the sample. Using featherweight forceps, place this material back in the sample jar.
 - c. If using the TOS beetle filter cup, rinse down the sides of the cup with ETOH, and place the filter mesh and all material on it back into the sample jar. Use 250 µm mesh, not the TOS mesh.
4. Check that sample label is still readable and inside the sample jar. Check that the external adhesive label/barcode label is on the outside of the sample jar.
5. Re-preserve sample with 95% ethanol/5% glycerol solution. Fill jar with liquid to prevent sample damage during shipping.
6. Close the sample jar tightly.
7. Carefully clean sieve or filter cup before decanting the next sample.
8. Continue until preservative in all samples has been replaced and proceed to Sample Shipping (SOP G).

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

E.3 Processing Samples – DNA

1. Change ethanol between 12 and 72 hours in the domain lab.
2. **Do not add glycerol** to DNA samples.
3. Wearing safety glasses and nitrile gloves, open field-preserved sample under fume hood.
4. Follow Section E.2 to change out the ethanol in the sample, with the exception of adding glycerol.
5. Replace ethanol, preserving as close to 95% as possible.
 - a. Container does not need to be filled to the top with liquid.
6. Close the sample jar tightly, place in -20 °C and dark until shipping. Proceed to SOP G.

E.4 Sample Storage

Samples may be stored at the domain support facility at room temperature or 4 °C until shipping. For shipping instructions see SOP G.

E.5 Ending the Processing Day

1. Equipment maintenance, cleaning and storage
 - a. Carefully clean and dry sieve to remove all organic debris.
 - b. Dry all equipment thoroughly before storage.

SOP F Data Entry and Verification

Mobile applications are the preferred mechanism for data entry. Data should be entered into the protocol-specific application as they are being collected, whenever possible, to minimize data transcription error and improve data quality. If available, adhesive barcode labels should be used and scanned into the mobile application. Mobile devices should be synced at the end of each field day, where possible; alternatively, devices should be synced immediately upon return to the Domain Support Facility. For detailed instructions on protocol specific data entry into mobile devices, see the NEON Internal Sampling Support Library (SSL).

Given the potential for mobile devices to fail under field conditions, it is imperative that paper datasheets are always available to record data. Paper datasheets should be carried along with the mobile devices to sampling locations at all times. As a best practice, field data collected on paper datasheets should be digitally transcribed within 7 days of collection or the end of a sampling bout (where applicable). However, given logistical constraints, the maximum timeline for entering data is within 14 days of collection or the end of a sampling bout (where applicable). See RD[04] for complete instructions regarding manual data transcription.

Data and sample IDs must be entered digitally and quality checked prior to shipping samples to an external lab.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

SOP G Sample Shipment

Information included in this SOP conveys science-based packaging, shipping, and handling requirements, not lab-specific or logistical demands. For that information, reference the CLA shipping document on NEON’s CLA intranet site.

1. Keep morphological taxonomy samples and DNA samples separate.
2. Seal jar lids with electrical tape prior to shipping. This helps prevent leaks and prevent ethanol fumes from turning labels black during shipment.
3. Place sealed sample jars into one or several gallon-sized resealable zip-top bags, grouped by site. Sample jars are acceptable “inner containers” required for shipping.
2. Line a Group II cardboard box with a heavy-duty trash bag.
3. Place all sample jars right-side up inside the trash bag, inside the Group II cardboard shipping box. Add Grade 2 Vermiculite in the trash bag liner as needed to take up excess space in container and cushion samples.
4. Navigate to the “Shipping Information for External Facilities” document on CLA’s NEON intranet site. Check whether items such as permits or cover letters are required in the shipment. Check this document often as instructions are subject to change.
5. Prepare a shipping inventory detailing the contents of the shipment, using the protocol-specific templates found on CLA’s NEON intranet site (RD[11]). Include a printed copy of the shipping inventory in the shipment box in a zip-top bag.
6. Save the inventory with the following naming convention:
 - “DXX_MOD_ShippingInventory_YYYYMMDD_XofX”
 - a. Example: “D05_INV_ShippingInventory_20161202_1of2”
7. Complete packing slip, address shipment, and ship ground to the destination(s) specified in the CLA “Shipping Information for External Facilities” document.
 - a. Follow instructions for shipping ETOH in limited quantity ground shipments in AD[03].
 - b. DNA samples do not need to be shipped on ice.
8. Email an electronic copy of the shipping manifest and tracking number to the email addresses listed in the CLA “Shipping Information for External Facilities” document, including the NEON CLA email address.

G.1 Handling Hazardous Material

Follow procedures for shipping ethanol in limited quantity ground shipments in AD[03].

G.2 Supplies/Containers

See section SOP G Steps 1-8 and Table 7 for specific shipping materials.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

G.3 Timelines and Conditions

Taxonomy samples: Shipping should occur within one week of sampling if possible, however samples may be held for up to 30 days at the domain support facility if necessary. Samples may be stored at the domain support facility room temperature or 4 °C until shipping. Samples are shipped ground at ambient temperature.

DNA samples: Shipping should occur within one week of sampling if possible, however samples may be held for up to 30 days in the dark at 4 °C at the domain support facility if necessary. Samples may be held for a maximum of 6 months if batch shipping is requested by the external lab. Samples are shipped overnight at ambient temperature.

G.4 Grouping/Splitting Samples

Group samples by site per bout in plastic bags. Samples from multiple sites may be sent in the same shipment. Macroinvertebrate samples may be shipped with zooplankton samples (RD[17]) if going to the same external lab.

G.5 Return of Materials or Containers

Include return shipping label if any shipping materials need to be returned to the domain support facility (e.g., cooler). Sample jars will not be returned.

G.6 Shipping Inventory

Shipments are to have a hardcopy of the per sample tab of the shipping inventory (RD[11]) sent in each box as well as an electronic shipping inventory that is emailed to the receiving laboratory and to the contact in NEON Collections and Laboratory Analysis at the time of shipment. Also include the shipment tracking number in the email. The shipping inventory must accurately document the physical samples inside the shipping container.

G.7 Laboratory Contact Information and Shipping/Receipt Days

See the Shipping Information for External Facilities on NEON’s CLA intranet site.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

7 REFERENCES

- Allan, J. D. 1995. *Stream Ecology: Structure and Function of Running Waters*. Kluwer Academic Publishers, Boston, MA. 388 pages.
- Angradi, T.R. (editor). 2006. *Environmental Monitoring and Assessment Program: Great River Ecosystems, Field Operations Manual*. EPA/620/R-06/002. U.S. Environmental Protection Agency, Washington, D.C.
- Baker, John R., David V. Peck, and Donna W. Sutton (editors). 1997. *Environmental Monitoring and Assessment Program Surface Waters: Field Operations Manual for Lakes*. EPA/620/R-97/001. U.S. Environmental Protection Agency, Washington, D.C.
- Barbour, M. T., Gerritsen, B. D. Snyder, and B. Stribling. 1999. Benthic Macroinvertebrate Protocols. Pages 7.1-7.34 *in* *Rapid Bioassessment Protocols for Use in Streams and Wadeable Rivers: Periphyton, Benthic Macroinvertebrates and Fish*, 2nd Edition. EPA 841-B-99-002. U.S. Environmental Protections Agency, Office of Water, Washington, D.C.
- Brooks, S. S. and A. J. Boulton. 1991. Recolonization dynamics of benthic macroinvertebrates after artificial and natural disturbances in an Australian temporary stream. *Australian Journal of Marine and Freshwater Research* **42**:295-308.
- Clausen, B. and B. J. F. Biggs. 1997. Relationships between benthic biota and hydrological indices in New Zealand streams. *Freshwater Biology*. **38**: 327-342.
- Cuffney, T. F., M. E. Gurtz, and M. R. Meador. 1993. *Methods for collecting benthic invertebrate samples as part of the National Water-Quality Assessment Program*. U.S. Geological Survey Open-File Report 93-406. Raleigh, NC.
- Dates, G. and J. Byrne. 1997. *Living Waters: Using Benthic Macroinvertebrates and Habitat to Assess Your River's Health*. River Watch Network, Montpelier, VT.
- DiFranco, J. 2006. *Protocols for Sampling Aquatic Macroinvertebrates in Freshwater Wetlands*. DEPLW0640. Maine Department of Environmental Protection, Bureau of Land and Water Quality, Portland, Maine.
- FDEP. 2011. *Sampling and use of Stream Condition Index (SCI) for assessing flowing waters: A primer*. DEP-SAS-001/11. Florida Department of Environmental Protection Bureau of Assessment and Restoration Support, Tallahassee, FL.
- Hauer, F. R. and V. H. Resh. 2006. Macroinvertebrates. Pages 435-463 *in* F. R. Hauer and G. A. Lamberti, editors. *Methods in Stream Ecology*, Second Edition. Academic Press, Boston, MA.
- Hynes, H. B. N. 2001. *The Ecology of Running Waters*. The Blackburn Press, Caldwell, NJ. 555 pages.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

- Jane, S. F., T. M. Wilcox, K. S. McKelvey, M. K. Young, M. K. Schwartz, W. L. Lowe, B. H. Letchers, and A. R. Whitley. Distance, flow, and PCR inhibition: eDNA dynamics in two headwater streams. *Molecular Ecology Resources*. **15**: 216-227.
- Lane, S. L. and R. G. Fay. 1997. Safety in Field Activities: U.S. Geological Survey Techniques of Water-Resources Investigations, Book 9, Chapter A9. Accessed 11 April 2013, at <http://pubs.water.usgs.gov/twri9A9/>.
- Laramie, M. B., D. S. Pilliod, C. S. Goldberg, and K. M. Strickler. 2015. Environmental DNA sampling protocol: Filtering water to capture DNA from aquatic organisms. *USGS Survey Techniques and Methods*, Book 2, Chapter 113. <http://dx.doi.org/10.3133/tm2A13>.
- Matthaei, C. D., U. Uhlinger, E. I. Meyer, and A. Frutiger. 1996. Recolonization by benthic invertebrates after experimental disturbance in a Swiss prealpine river. *Freshwater Biology* **35**: 233-248.
- Merritt, R. W. and K. W. Cummins. 2006. Trophic Relationships of Macroinvertebrates. Pages 585-609 in F. R. Hauer and G. A. Lamberti, editors. *Methods in Stream Ecology*, Second Edition. Academic Press, Boston, MA.
- Moulton, S. R., II, J. G. Kennen, R. M. Goldstein, and J. A. Hambrook. 2002. Revised protocols for sampling algal, invertebrate, and fish communities as part of the National Water-Quality Assessment Program. Open-File Report 02-150. U.S. Geological Survey, Reston, VA.
- Slavik, K., B. J. Peterson, L. A. Deegan, W. B. Bowden, A. E. Hershey, and J. E. Hobbie. 2004. Long-term responses of the Kuparuk River ecosystem to phosphorus fertilization. *Ecology* **85**:939-954.
- Stein, E. D., B. P. White, R. D. Mazor, P. E. Miller, and E. M. Pilgrim. 2013. Evaluating ethanol-based sample preservation to facilitate use of DNA barcoding in routine freshwater biomonitoring programs using benthic macroinvertebrates. *PLoS ONE* **8**: e51273.
- USEPA. 2002. Standard operating procedure for benthic invertebrate field sampling. EPA LG406. U.S. Environmental Protection Agency, Washington, D.C.
- USEPA. 2009. National Lakes Assessment: A Collaborative Survey of the Nation's Lakes. EPA 841-R-09-001. U.S. Environmental Protection Agency, Office of Water and Office of Research and Development, Washington, D.C.
- USEPA. 2011. National Lakes Assessment. Field Operations Manual. EPA 841-B-11-003. U.S. Environmental Protection Agency, Washington, D.C.
- Wetzel, R. G. 2001. *Limnology: Lake and River Ecosystems*, 3rd Edition. Academic Press, San Diego, CA. 1006 pages.

<i>Title:</i> AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		<i>Date:</i> 01/19/2018
<i>NEON Doc. #:</i> NEON.DOC.003046	<i>Author:</i> S. Parker	<i>Revision:</i> C

APPENDIX A DATASHEETS

The following datasheets are associated with this protocol:

Table 9. Datasheets associated with this protocol

NEON Doc. #	Title	Mobile Application
NEON.DOC.003043	Datasheets for AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling	(AOS) Macroinvertebrate [PROD]
NEON.DOC.001646	General AQU Field Metadata Sheet	(AOS) Field Metadata and Gauge Height [PROD]
NEON.DOC.002494	Datasheets for AOS Shipping Inventory	Shipping App [PROD]

Datasheets can be found in Agile or the NEON Document Warehouse, user guides for mobile applications may be found in NEON’s internal sampling support library.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

APPENDIX B QUICK REFERENCES

B.1 Steps for Macroinvertebrate Sampling

- Step 1** – Check the macroinvertebrate field sampling kit to make sure all supplies are packed.
- Step 2** – Prepare internal (below), external sample labels (2” x 4”), and barcode labels (if available).
- Step 3** – Ensure the General AQU Field Metadata (RD[06]) is completed per field site visit (mobile app or datasheet).
- Step 4** – Determine habitat sampling locations from the Rapid Habitat Assessment (RD[09]).
- Step 5** – Determine sampler type based on the habitats present and the order of preference for sampling habitats.

Wadeable streams

1. Riffles (Surber or Hess)
2. Runs (Surber, Hess, or modified kicknet)
3. Snags (D-frame snag net)
4. Pools (corer, Hess, or petite ponar)

Lakes/Rivers – Benthic

1. Petite ponar
2. Modified Kicknet

Lakes/Rivers – Littoral

1. Aquatic plant beds or floating mats (D-frame net), dead vegetation is acceptable.
2. Snags/large woody debris (Modified kicknet snag sampler)

Step 6 – Collect taxonomy samples (**Wadeable Streams**: 5 per dominant habitat type, 3 per second-most dominant habitat type; **Lakes/Rivers**: 3 in benthic sediments, 5 in the dominant littoral habitat type with the appropriate sampler). Collect DNA samples (**Wadeable Streams**: 3 per dominant habitat type; **Lakes/Rivers**: 3 per dominant littoral habitat type (with samples sampler as taxonomy)).

Step 7 – Elutriate and pour sample over sieve or sieve bucket.


Step 8 – Transfer sample from sieve to sample jars

Step 9 – Preserve with 95% ethanol to a final concentration of ~70% ethanol in the field.


Step 10 – Taxonomy: Change preservative and add glycerol at the Domain Support Facility within 12-72 hours of sample collection. DNA: Change preservative (no glycerol) at the Domain Support Facility within 12-72 hours of sample collection.

Step 11 – Store appropriately and ship samples to external facility.

B.2 Determining Habitat to Sample in Wadeable Streams



B.3 Decision Tree for Lakes/Rivers



Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

APPENDIX C REMINDERS

Before heading into the field: Make sure you...

- Collect and prepare all equipment, including sample jars and labels.
- Pre-print waterproof labels, small adhesive labels, and barcode labels if available.
- Check for holes in nets and sieve, assure that both are clean and free of debris.
- Bleach clean all equipment between sites for DNA sampling.
- Fill 1 L HDPE bottles with 95% undenatured ethanol. Cap tightly and clearly label bottle. Transport to the field following EHS guidelines.

Sample collection: Be sure to...

- Determine the habitats to sample based on the Stream Morphology or rapid habitat assessment, Bathymetry and Riparian Maps.
- Choose the appropriate sampler.
- Start sampling at the bottom of the reach in flowing water, working upstream so as not to decrease visibility and cause invertebrates to drift (**wadeable streams**).
- Spread samples out along the reach or among riparian sections.
- Do not sample anywhere you or other field people/animals have walked in the reach, recently sampled, or locations that appear recently disturbed.
- Lakes/Rivers:** Collect 3 samples from benthic sediments and 5 samples from the dominant littoral habitat for taxonomy. Collect 3 samples from the dominant littoral habitat for DNA.
- Wadeable Streams:** Collect 5 samples from the dominant habitat type and 3 samples from the secondary habitat type for taxonomy. Collect 3 samples from the dominant habitat type for DNA.

Sample preservation: Be sure to...

- Preserve the samples streamside/lakeside or at the vehicle to reduce predation.
- Change the preservative (and add glycerol for taxonomy only) within 12-72 hours of field sampling.
- Fill jar with ETOH to prevent destruction of organisms during shipping.

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

APPENDIX D ESTIMATED DATES FOR ONSET AND CESSATION OF SAMPLING

Preliminary date ranges for biological sampling bouts. General guidelines for developing these dates are presented in the NEON Aquatic Sample Strategy Document (RD[07]). Also see the Site Specific Sampling Strategy Document on NEON’s FOPS intranet site.

Domain	Site	Bout 1	Bout 2	Bout 3
D01	Hop Brook	11Apr-9May	9Jul-6Aug	30Oct-31Oct
D02	Lewis Run	19Mar-16Apr	5Jul-2Aug	18Oct-15Nov
D02	Posey Creek	19Mar-16Apr	5Jul-2Aug	18Oct-15Nov
D03	Flint River	21Feb-21Mar	27Jun-25Jul	7Oct-4Nov
D03	Lake Barco	9Feb-9Mar	27Jun-25Jul	29Oct-26Nov
D03	Lake Suggs	9Feb-9Mar	27Jun-25Jul	29Oct-26Nov
D04	Rio Guilarte	26Jan-23Feb	21Jun-19Jul	9Nov-7Dec
D04	Rio Cupeyes	24Jan-21Feb	21Jun-19Jul	10Nov-8Dec
D05	Crampton Lake	20Apr-18May	5Jul-2Aug	13Sep-11Oct
D05	Little Rock Lake	20Apr-18May	5Jul-2Aug	13Sep-11Oct
D06	Kings Creek	23Mar-20Apr	3Jul-31Jul	30Oct-31Oct
D06	McDiffett Creek	23Mar-20Apr	3Jul-31Jul	30Oct-31Oct
D07	Leconte Creek	15Mar-12Apr	30Jun-28Jul	12Oct-9Nov
D07	Walker Branch	9Mar-6Apr	1Jul-29Jul	19Oct-16Nov
D08	Mayfield Creek	5Mar-2Apr	29Jun-27Jul	31Oct-28Nov
D08	Black Warrior River	19Feb-19Mar	27Jun-25Jul	31Oct-28Nov
D08	Tombigbee River	22Feb-22Mar	26Jun-24Jul	2Nov-30Nov
D09	Prairie Lake	18Apr-16May	5Jul-2Aug	11Sep-9Oct
D09	Prairie Pothole	20Apr-18May	5Jul-2Aug	11Sep-9Oct
D10	Arikaree River	21Mar-18Apr	4Jul-1Aug	20Sep-18Oct
D11	Pringle Creek	17Feb-17Mar	29Jun-27Jul	23Oct-20Nov
D11	Blue River	7Mar-4Apr	1Jul-29Jul	12Oct-9Nov
D12	Blacktail Deer Creek	1May-29May	13Jul-10Aug	30Aug-27Sep
D13	Como Creek	20May-17Jun	14Jul-11Aug	30Aug-27Sep
D13	West St. Louis Creek	2May-30May	5Jul-2Aug	3Sep-1Oct
D14	Sycamore Creek	17Feb-17Mar	29Jun-27Jul	21Oct-18Nov
D15	Red Butte Creek	29Mar-26Apr	6Jul-3Aug	29Sep-27Oct
D16	McRae Creek	10Apr-8May	11Jul-8Aug	23Sep-21Oct
D16	Martha Creek	6Apr-4May	5Jul-2Aug	22Sep-20Oct
D17	Teakettle 2 Creek	14Apr-12-May	8Jul-5-Aug	23Sep-21Oct
D17	Upper Big Creek	14Apr-12-May	8Jul-5-Aug	23Sep-21Oct
D18	Oksrukuyik Creek	21May-18Jun	29Jun-27Jul	7Aug-4Sep
D18	Toolik Lake	21May-18Jun	29Jun-27Jul	6Aug-3Sep
D19	Caribou Creek	2May-30May	26Jun-24Jul	18Aug-15Sep

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

APPENDIX E SITE-SPECIFIC INFORMATION: HABITAT AND SAMPLER RECOMMENDATIONS

For more information see the Site Specific Sampling Strategy Document on NEON’s FOPS intranet site.

Domain	Site	Habitat 1 (5 reps)	Habitat 2 (3 reps)
D01	Hop Brook	Riffle (Surber)	Pool (corer)
D02	Lewis Run	Run (core)	Riffle (Surber)
D02	Posey Creek	Riffle (Surber)	Pool (Hess)
D03	Flint River	Littoral (LWD)	Benthic (petite ponar)
D03	Lake Barco	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D03	Lake Suggs	Littoral (D-net floating sweep)	Benthic (petite ponar)
D04	Rio Guilarte	Riffle (Surber)	Pools (Hess)
D04	Rio Cupeyes	Riffle (Surber)	Run (Surber)
D05	Crampton Lake	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D05	Little Rock Lake	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D06	Kings Creek	Riffle/run (Surber)	Pools (corer)
D06	McDiffett Creek	Riffle (Surber)	NA
D07	Leconte Creek	Riffle (Surber)	Pool (corer)
D07	Walker Branch	Riffle (Surber)	Run (Surber)
D08	Mayfield Creek	Riffle/run (snags)	Run (core)
D08	Black Warrior River	Littoral (LWD)	Benthic (petite ponar)
D08	Tombigbee River	Littoral (LWD)	Benthic (petite ponar)
D09	Prairie Lake	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D09	Prairie Pothole	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D10	Arikaree River	Run (modified kicknet)	Pool (core)
D11	Pringle Creek	Run (core)	Riffle (Surber)
D11	Blue River	Run (modified kicknet)	Riffle (Surber)
D12	Blacktail Deer Creek	<i>tbd</i>	<i>tbd</i>
D13	Como Creek	Riffle (Surber)	Run (modified kicknet)
D13	West St. Louis Creek	Riffle (Surber)	Pool (core)
D14	Sycamore Creek	Run (Surber)	Pool (core)
D15	Red Butte Creek	Run (Hess)	Step pool (Hess)
D16	McRae Creek	Step pool/Riffle (Surber)	Step pool/Pool (Surber)
D16	Martha Creek	<i>tbd</i>	<i>tbd</i>
D17	Teakettle 2 Creek	<i>tbd</i>	<i>tbd</i>
D17	Upper Big Creek	<i>tbd</i>	<i>tbd</i>
D18	Oksrukuyik Creek	Run (modified kicknet)	Riffle (Surber)
D18	Toolik Lake	Littoral (D-net benthic sweep)	Benthic (petite ponar)
D19	Caribou Creek	Run (modified kicknet)	Riffle (Surber)

Title: AOS Protocol and Procedure: Aquatic Macroinvertebrate Sampling		Date: 01/19/2018
NEON Doc. #: NEON.DOC.003046	Author: S. Parker	Revision: C

APPENDIX F PAPER DATASHEET EXAMPLES

See also RD[05] for blank paper datasheets.

NEON Aquatic Benthic Invertebrate Collection										
Site ID: BARC			Sampling protocol: NEON.DOC.003046 Rev.: C							
Date: 2017-09-28			Recorded by: sparker@battelleecology.org							
Local time: 10:30			Collected by: jstewart@Field-ops.org							
Sampling impractical ?	Location ID	Habitat type	Sampler type	Sample number	Substratum size class	Sample ID	DNA sample collected?	*Ponar depth (m)	*Snag length (cm)	*Snag diameter (cm)
	in	pelagic	petite ponar	1	NA	BARC.20170928.ponar.1		2.10		
	ot	pelagic	petite ponar	2	NA	BARC.20170928.ponar.2		1.40		
	c0	pelagic	petite ponar	3	NA	BARC.20170928.ponar.3		1.20		
	02-Riparian Point	littoral	benthic sweep	2	NA	BARC.20170928.sweep.2				
	02-Riparian Point	littoral	benthic sweep	2	NA	BARC.20170928.sweep.2.DNA	yes			
	04-Riparian Point	littoral	benthic sweep	4	NA	BARC.20170928.sweep.4				
	06-Riparian Point	littoral	benthic sweep	6	NA	BARC.20170928.sweep.6				
	06-Riparian Point	littoral	benthic sweep	6	NA	BARC.20170928.sweep.6.DNA	yes			
	08-Riparian Point	littoral	benthic sweep	8	NA	BARC.20170928.sweep.8				
	10-Riparian Point	littoral	benthic sweep	10	NA	BARC.20170928.sweep.10				
	10-Riparian Point	littoral	benthic sweep	10	NA	BARC.20170928.sweep.10.DNA	yes			