

<i>Title:</i> NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		<i>Date:</i> 06/23/2014
<i>NEON Doc. #:</i> NEON.DOC.001306	<i>Author:</i> E. Ayres	<i>Revision:</i> A

NEON PROCEDURE AND PROTOCOL: PRODUCING TIS SOIL ARCHIVE SUBSAMPLES FOR USERS

PREPARED BY	ORGANIZATION	DATE
Edward Ayres	FIU	08/27/2013

APPROVALS	ORGANIZATION	APPROVAL DATE
Hanne Buur	PSE	06/20/2014

RELEASED BY	ORGANIZATION	RELEASE DATE
Stephen Craft	PSE	06/23/2014

See configuration management system for approval history.

© 2014 NEON Inc. All rights reserved.



<i>Title:</i> NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		<i>Date:</i> 06/23/2014
<i>NEON Doc. #:</i> NEON.DOC.001306	<i>Author:</i> E. Ayres	<i>Revision:</i> A

Change Record

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
A	06/23/2014	ECO-01356	Initial release

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

TABLE OF CONTENTS

1 DESCRIPTION.....1

1.1 Purpose 1

1.2 Scope..... 1

2 RELATED DOCUMENTS AND ACRONYMS1

2.1 Applicable Documents 1

2.2 Reference Documents..... 1

2.3 External References 2

2.4 Acronyms 2

3 BACKGROUND AND OBJECTIVES2

3.1 Background 2

3.2 Science Requirements..... 2

3.3 Data Products..... 3

4 PROTOCOL3

4.1 Protocol Assumptions 4

5 QUALITY ASSURANCE AND QUALITY CONTROL.....4

6 DECISION TREE5

7 SAFETY5

8 PERSONNEL REQUIREMENTS.....5

9 TRAINING REQUIREMENTS.....5

10 FIELD STANDARD OPERATING PROCEDURE5

11 LAB STANDARD OPERATING PROCEDURE6

11.1 Timing..... 6

11.2 Lab Procedure 7

11.2.1 Equipment and Materials..... 7

11.2.2 Preparation 7

11.2.3 Sample Processing in the Lab..... 7

11.2.4 Sample Preservation 9

11.2.5 Sample Shipping..... 9

11.2.6 Data Handling..... 9

<i>Title:</i> NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		<i>Date:</i> 06/23/2014
<i>NEON Doc. #:</i> NEON.DOC.001306	<i>Author:</i> E. Ayres	<i>Revision:</i> A

11.2.7 Refreshing the Laboratory Supplies 10

11.2.8 Laboratory Maintenance, Cleaning, and Storage 10

12 REFERENCES10

APPENDIX A FIELD DATA SHEETS11

APPENDIX B LAB DATA SHEETS.....12

APPENDIX C CONSIDERATIONS FOR IMPLEMENTATION13

LIST OF TABLES AND FIGURES

Table 1. Decision tree associated with producing soil subsamples for TIS Soil Archive users 5

Table 2. Materials and supplies required for the procedure..... 7

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

1 DESCRIPTION

1.1 Purpose

The primary purpose of this document is to provide a change controlled version of Observatory protocols for creating soil subsamples for users of the TIS Soil Archive and serve as the version used for external review by subject-matter experts. This document provides the content for training for NEON staff and contractors. Content changes (i.e. changes in particular tasks or safety practices) occur via this change controlled document, not through field manuals or training materials.

1.2 Scope

This document relates to tasks for producing soil subsamples for users of the TIS Soil Archive, as well as directly associated activities and safety practices. This document assumes that a request for samples from the TIS Soil Archive has been received and approved by NEON. This document assumes that users will be sent subsamples from the TIS Soil Archive and that this material will not be returned to the Archive. This document does not describe:

- General safety practices
- Site-specific safety practices
- General maintenance

2 RELATED DOCUMENTS AND ACRONYMS

2.1 Applicable Documents

Applicable documents contain information that shall be applied in the current document. Examples are higher level requirements documents, standards, rules and regulations.

AD [01]	NEON.DOC.001307	TIS Soil Pit Sampling Protocol
AD [02]	NEON.DOC.000325	Field and Lab Procedure and Protocol: TIS Soil Archiving
AD [03]		
AD [04]		

2.2 Reference Documents

Reference documents contain information complementing, explaining, detailing, or otherwise supporting the information included in the current document.

RD [01]	NEON.DOC.000008	NEON Acronym List
RD [02]	NEON.DOC.004316	EHS Safety Policy and Program Manual
RD [03]		
RD [04]		

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

2.3 External References

External references contain information pertinent to this document, but are not NEON configuration-controlled. Examples include manuals, brochures, technical notes, and external websites.

ER [01]	
ER [02]	
ER [03]	

2.4 Acronyms

NEON	National Ecological Observatory Network
P&P	Procedure and Protocol
TBD	To be determined
TIS	NEON Terrestrial Instrument System
USDA APHIS	United States Department of Agriculture Animal and Plant Health Inspection Service

3 BACKGROUND AND OBJECTIVES

3.1 Background

Archived soil samples are necessary to serve as a reference of current soil physical and chemical conditions, and for use with future analytical techniques that are yet to be derived or invented (Boone et al. 1999). Previous scientific studies using archived soils have produced a wide range of novel findings, including:

- Assessing changes in lead pollution following the introduction of unleaded gasoline (Friedland et al. 1992);
- Refining estimates of organic matter turnover using ¹⁴C bomb carbon (Trumbore 1993);
- Measuring the accumulation of atmospheric inputs such as sulfur (Lapenis et al. 2004) or pesticides, including DDT, in soils throughout the 20th century (Meijer et al. 2001).

In addition, archived soil samples and associated measurement data can be used to calibrate new techniques/instruments/models to data collected with earlier methods or technologies.

The Terrestrial Instrument System (TIS) Soil Archive consists of air-dried soil collected and stored by soil horizon from a single soil pit at each NEON site. Samples in the TIS Soil Archive will be stored for NEON’s 30-year Operational window. The archive is a resource for the scientific community and researchers are expected to request material from the archive for analysis.

3.2 Science Requirements

This protocol fulfills the following Observatory science requirements: NEON.TIS.4.1009

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

3.3 Data Products

There are currently no data products (DPs) associated with TIS soil archive samples because no measurements are currently planned to be made on these samples by NEON. The archived samples are a resource that NEON shall provide to the community and could provide significant scientific information in the future. There are however, chemical and physical analyzes preformed on samples collected in the same location, soil horizon, and time, which are associated with L1 DPs.

4 PROTOCOL

As described above, the samples in the TIS soil archive will constitute a valuable resource to the scientific community, as the samples provide information on soil conditions at the time of collection and an opportunity to calibrate new techniques/instruments/models to data collected with earlier methods or technologies.

This document describes the how TIS Soil Archive samples are processed to produce a subsample for an Archive User. A description of how soil samples for the TIS Soil Archive shall be collected in the field is given in AD[01] and how they are processed to get into the archive is described in AD[02]. Briefly, independent soil samples (~8 L at field moisture) will be collected from each soil horizon exposed in a single soil pit at each NEON core and relocatable site. At most sites, the soil pit will extend 2 m deep or to bedrock, however, it will extend 3 m deep at sites with permafrost. Mineral soil will be air-dried and sieved (2 mm) prior to archiving, while organic soils will be air-dried and broken up and mixed by hand prior to archiving. Because only one soil sample will be archived per soil horizon at each site, the TIS Soil Archive will be useful for regional and continental scale studies, but not local scale studies due to the lack of spatial sampling at that local-scale. The archived samples will be suitable for a range of physical and chemical analyses, but will typically not be suitable for assessments of soil biology or structure due to the way they are processed and stored.

To minimize contamination, all materials that come into contact with the soil samples (*e.g.*, trays for drying, spoon/spatulas, storage containers) shall be clean and un-corroded. Materials made of glass and corrosion resistant metal, not plastic, shall be used to process and store samples whenever possible. Glass and metal are recommended since they are unlikely to contaminate the soil samples or compromise any future analyses that may be performed on the samples. To avoid cross-contamination among soil samples, all materials shall be cleaned prior to processing the next sample. If soap is used for cleaning it shall be phosphate-free (*e.g.* Alconox). Quaternary ammonia must NOT be used for sterilizing soil or equipment used for the TIS Soil Archive to minimize the risk of contaminating the archive samples.

Archive users often request more material than they actually need to guard against spillage or other accidents. As a result some researchers have suggested sending the entire archive sample to the user so that they can take the exact quantity required and return the remaining material to the archive after

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

their analyses are complete (Boone et al. 1999). However, sending out the entire sample (or a large fraction of it) risks the loss or contamination of a large amount of the archived material (e.g., lost or damaged in transit). In addition, it is difficult to ensure the sample storage requirements are met once the sample has left the archive. Because of these concerns, when a user requests material from the TIS Soil Archive, the archive samples will be subsampled and only the subsample will be sent to the user. Any unused material that may be returned to the TIS Soil Archive by the user will NOT be re-combined with the archived sample due to concerns that it may have become contaminated or otherwise altered after it was removed from the archive. Briefly, the process for creating a soil subsample for a TIS Soil Archive user will involve mixing the sample to ensure it is homogeneous, weighing out the quantity required by the user, and returning the remaining soil to its storage container. The subsample will then be shipped to the user.

Soil from several NEON sites (e.g., Hawaii and Puerto Rico) must be quarantined according to USDA APHIS regulations. Furthermore, soils samples must be transported following USDA packing standards. To simplify this protocol and minimize the risk of accidental release of quarantined soil, NEON shall treat soil from all sites as quarantined and all parts of this protocol shall comply with NEON’s USDA APHIS soil permit (see permit for details). This includes sterilizing or destroying, using an approved method, anything that came into contact with the soil. Refer to NEON’s USDA APHIS permit for instructions to sterilize soil and material that came into contact with soil prior to disposal.

4.1 Protocol Assumptions

For the purpose of this document, we assume that the TIS soil archive will be housed at NEON headquarters. We assume that a request for material from the soil archive was submitted to NEON, was approved, and that NEON has received approval from USDA APHIS to send the material requested to the user.

Soils from several NEON sites is quarantined by USDA APHIS, including those from Hawaii, Puerto Rico, and several sites in the southeast US where fire ants are present. As a result, we assume all soil samples for the TIS soil archive shall be treated as quarantined soil to simplify the processing procedures and minimize the risk of accidental release.

5 QUALITY ASSURANCE AND QUALITY CONTROL

The weight of soil in a TIS Soil Archive sample shall be compared to the weight of material sent to the user and the weight returned to the archive to ensure that all material has been accounted for.

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

6 DECISION TREE

Table 1. Decision tree associated with producing soil subsamples for TIS Soil Archive users indicating how to respond to a delay in processing the samples

Delay	Action	Adverse outcome	Outcome for TIS soil archive
>2 hours	Return all sample material to its storage container and return the container to the archive.	Slightly elevated risk of sample spillage due to repeated transfer.	None (assuming no material is lost)

7 SAFETY

Personnel working at a NEON site should be familiar with and practice safe field and lab work as outlined in the EHS Safety Policy and Program Manual. Additional safety issues associated with this field procedure are outlined below. All employees have the responsibility and right to stop their work in unsafe conditions.

Laboratory safety training is required prior to operating laboratory equipment.

8 PERSONNEL REQUIREMENTS

Demonstrated ability to follow standard operating procedures in a laboratory setting. Experience using standard laboratory equipment (*e.g.*, balances, drying ovens). Experience working with environmental samples (*e.g.*, soil, plant, or water samples) is desirable. Experience working with quarantined samples is desirable.

9 TRAINING REQUIREMENTS

The training plan for this procedure is to read this document, read NEON’s USDA APHIS soil permit, discuss the procedure with FIU personnel, and contact FIU personnel when issues or concerns arise. It is essential that any personnel undertaking this procedure are familiar with the current version of NEON’s USDA APHIS soil permit, as this permit dictates how to transport soil samples, and how quarantined soil, and material that has come into contact with quarantined soil, can be safely disposed of or sterilized. Any personnel undertaking this procedure for the first time shall be supervised by personnel that are familiar with the procedure. Note that the USDA APHIS soil permit can be updated at any time, therefore, close communication between NEON EHS and personnel performing this protocol is required.

10 FIELD STANDARD OPERATING PROCEDURE

The procedure for collecting samples for the TIS soil archive in the field is described in AD[01].

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

11 LAB STANDARD OPERATING PROCEDURE

The procedure shall always fully comply with all restrictions outlined in NEON’s USDA APHIS soil permit. If a discrepancy is identified between the procedure outlined in this document (or other NEON documents) and the USDA APHIS soil permit, the permit has precedence. If this occurs, contact a FIU Manager through the NEON Problem Reporting and Tracking system.

The laboratory procedure has the following goals: 1) thoroughly mix the sample to ensure that the sample is homogeneous; 2) weigh the quantity of material requested into the container that will be sent to the user; 3) return the remaining material to the TIS Soil Archive container and return it to the archive; 4) record and enter all data and metadata associated with each sample; and 5) ship the subsample to the user.

Under no circumstances should the floor (or walls) of the soil archive room be either waxed, or have the use of wax strippers (NH₄, ammonia) be used for the life of the soil archive. This is a requirement, and must be communicated to building managers, FCC, cleaning staff etc. Use of these materials can contaminate the entire archive.

11.1 Timing

- NEON aims to send approved sample requests to users within 2 months of the request. Since the request first has to be approved by NEON, and then USDA APHIS has to provide approval to NEON to ship material to the user, we assume only 1 month will be available to produce the subsamples for the user. Therefore, processing the samples should begin shortly after a request is fully approved and should be completed within 1 month of being fully approved.
- Additional time may be required if special sample containers are needed (e.g., if they must be made of a certain material).
- Metadata relating to any step in the processing of samples for the TIS soil archive shall be entered within 1 business day of completion of that step to minimize mistakes in the metadata (e.g., forgetting how a particular sample was processed).

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

11.2 Lab Procedure

11.2.1 Equipment and Materials

Table 2. Materials and supplies required for the procedure

Item Description	Quantity per sampling event	Hazardous Chemical
Laboratory gloves (e.g., latex or nitrile)	2/sample	No
Printable labels	1/sample	No
Calibrated mass balance (≤ 0.1 g accuracy; ≥ 2 kg capacity)	1	No
Set of calibration standards for mass balance	1	No
Sealable containers for subsamples	1/sample	No
Metal spatulas or spoons	4	No
Data sheets	1 set	No
Pencil	1/technician	No
Ethanol (95%)	0.5 liters	Yes
Paper towels	~4	No
Leak-proof shipping container	As needed	No

11.2.2 Preparation

Ensure that you are familiar with the current version of NEON’s USDA APHIS soil permit. Ensure that all storage, processing, and cleaning locations comply with NEON’s USDA APHIS permit at all times (see permit for details).

Ensure that the processing area is clean and that there is sufficient space prior to beginning sample processing. This includes making sure that the floor has been swept so that if a sample is spilt, it can be recovered with minimal contamination (see Appendix C).

11.2.3 Sample Processing in the Lab

Always wear gloves when handling soil for the TIS soil archive. Gloves can be removed and destroyed using an appropriate method as defined in NEON’s USDA APHIS soil permit, whereas it is much harder to appropriately dispose of quarantined soil on your hands.

It is preferable that all data and metadata recorded during this procedure be entered directly into electronic form (rather than a data sheet, which must then be transcribed to electronic form), as this will eliminate a potential source of errors. If a data sheet is used, the original data sheet shall be archived within the NEON soil archive.

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

All materials (including trays, sieves, and spoons/spatulas) must be cleaned in between processing each sample to avoid cross-contamination. If soap is used for cleaning it shall be phosphate-free. Do not use quaternary ammonia for sterilizing soil or equipment used for the TIS Soil Archive to minimize the risk of contaminating the archive samples. Equipment or material used in procedures where quaternary ammonia is used must not be used for processing or storing TIS Soil Archive samples. Immediately prior to use, all materials shall be wiped with 95% ethanol and placed in a clean location prior to use.

The TIS Soil Archive contains at least 4 jars of material for each soil horizon at a NEON site. These jars have the same label, except the last number which is 1, 2, 3, or 4 (or higher if more jars were required). Requests for soil shall always be fulfilled with material from the first (“1”) jar until that jar is exhausted, at which point the second (“2”) jar shall be used until that jar is exhausted, and so on.

1. Prepare printed label for each subsample. The subsamples sent to TIS Soil Archive users shall match the label of the corresponding soil archive sample label, but with the request number appended to the end. For examples, if the archive sample is:

2_Blandy_Pit1_14-23_Archive_Ap2_1

then the subsample for the user shall be labeled:

2_Blandy_Pit1_14-23_Archive_Ap2_1_XXXXX

where XXXXX is a 5-digit number matching the request number.

2. Ensure the balance is level and was calibrated within the last 12 months.
3. Put on gloves. Weigh and record the weight in grams of the TIS Soil Archive sample including the jar lid and compare the weight to the last recorded weight for that sample. If the weight differs by >1 g do not proceed with that sample and contact the FIU Manager, otherwise proceed to the next step.
4. Tip the sealed jar containing the sample onto its side and rotate the sample 4 times around its long axis to homogenize the material in the jar. If it appears that the sample is still not homogenous this step can be repeated until the sample appears homogeneous.
5. Label the container that will be sent to the user and record its weight in grams, including container lid.
6. Remove the container lid and tare the balance. Then weigh the requested weight of soil into the container and record the weight in grams.
7. Return all remaining soil to the TIS Soil Archive jar. Weigh the jar (including lid) and record the weight in grams.

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

8. Ensure that all soil is accounted using the following equation:

$$x = A - B - D$$

Where

A is the initial weight of the TIS Soil Archive jar (*Step 3*)

B is the final weight of the TIS Soil Archive jar (*Step 8*)

D is the weight of soil added to the container (*Step 7*)

x is the weight of soil that is unaccounted for

If *x* is ≤ 0.15 g and ≥ -0.15 g we assume all soil was accounted for, with the discrepancy due to loss of trace amounts during processing and uncertainty introduced by the balance. If *x* is outside this range check all the weights to determine the mistake. If the discrepancy cannot be resolved contact the FIU Manager.

9. Once all the subsamples for a TIS Soil Archive user have been prepared they shall be sent to the user via a method that complies with the current USDA APHIS permit held by NEON. At present this specifies that each sample shall be placed in a leak-proof container, which will be placed within a second leak-proof container for shipping.

11.2.4 Sample Preservation

Samples shall be stored in the TIS soil archive when not in use. Samples shall always be returned to their allocated location in the archive (*e.g.*, shelf 4, cabinet 2). This is important to ensure that samples can be found quickly and easily whenever requested.

Samples for a user shall be stored in the TIS Soil Archive until they are ready to be sent to the user. Samples shall never be stored on the floor to minimize the risk of loss due to flooding. To minimize degradation of soil samples due to light exposure lights shall be switched off when the archive is not in use.

11.2.5 Sample Shipping

The shipping procedure shall comply with NEON's USDA APHIS Permit to Receive Soil.

11.2.6 Data Handling

It is preferable that all data and metadata recorded during this procedure be entered directly into electronic form (rather than a data sheet, which must then be transcribed to electronic form), as this will eliminate one source of errors.

If physical datasheets are used, all data and metadata shall be entered in electronic form to the appropriate database (TBD) within 1 day.

Title: NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		Date: 06/23/2014
NEON Doc. #: NEON.DOC.001306	Author: E. Ayres	Revision: A

11.2.6.1 Metadata

Metadata for this protocol shall include the date that the user’s subsample was produced, the name of the technician, as well as any relevant notes.

11.2.7 Refreshing the Laboratory Supplies

Order new supplies as user requests are received.

11.2.8 Laboratory Maintenance, Cleaning, and Storage

Prior to beginning this procedure and at the end of every day when samples are processed, all work surfaces shall be cleaned with 95 % ethanol and the floor shall be cleaned (*e.g.*, swept).

All materials shall be placed in labeled locations (*i.e.*, draws, cupboards, racks) when not in use.

All waste that came into contact with soil shall be disposed of in compliance with NEON’s USDA APHIS permit.

12 REFERENCES

Boone, R. D., D. F. Grigal, P. Sollins, R. J. Ahrens, and D. E. Armstrong. 1999. Soil sampling, preparation, archiving, and quality control. Pages 3-28 *in* G. P. Robertson, D. C. Coleman, C. S. Bledsoe, and P. Sollins, editors. Standard Soil Methods for Long-Term Ecological Research. Oxford University Press, Oxford.

Friedland, A. J., B. W. Craig, E. K. Miller, G. T. Herrick, T. G. Siccama, and A. H. Johnson. 1992. Decreasing lead levels in the forest floor of the northeastern USA. *Ambio* 21:400-403.

Lapenis, A. G., G. B. Lawrence, A. A. Andreev, A. A. Bobrov, M. S. Torn, and J. W. Harden. 2004. Acidification of forest soil in Russia: From 1893 to present. *Global Biogeochemical Cycles* 18.

Meijer, S. N., C. J. Halsall, T. Harner, A. J. Peters, W. A. Ockenden, A. E. Johnston, and K. C. Jones. 2001. Organochlorine pesticide residues in archived UK soils. *Environmental Science & Technology* 35:1989-1995.

Trumbore, S. E. 1993. Comparison of carbon dynamics in tropical and temperate soils using radiocarbon measurements. *Global Biogeochemical Cycles* 7:275-290.

<i>Title:</i> NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		<i>Date:</i> 06/23/2014
<i>NEON Doc. #:</i> NEON.DOC.001306	<i>Author:</i> E. Ayres	<i>Revision:</i> A

APPENDIX A FIELD DATA SHEETS

See AD[01].

<i>Title:</i> NEON Procedure and Protocol: Producing TIS Soil Archive Subsamples for Users		<i>Date:</i> 06/23/2014
<i>NEON Doc. #:</i> NEON.DOC.001306	<i>Author:</i> E. Ayres	<i>Revision:</i> A

APPENDIX C CONSIDERATIONS FOR IMPLEMENTATION

If an entire sample is spilt, try to salvage parts of the sample that are least likely to have been contaminated. For example, if a subsample jar is dropped and smashes and the soil is in a pile on the floor, collect the soil from the top of the pile (*i.e.*, that does not appear to have come into direct contact with the floor). Record details of the incident in the metadata and note the quantity of sample that was salvaged. This subsample should only be used after all other material from the same sample has been used.