

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

TOS PROTOCOL AND PROCEDURE: PLANT BELOWGROUND BIOMASS SAMPLING

PREPARED BY	ORGANIZATION	DATE
Courtney Meier	SCI	10/17/2016

APPROVALS	ORGANIZATION	APPROVAL DATE
Kate Thibault	SCI	05/14/2018
Mike Stewart	SYE	05/10/2018

RELEASED BY	ORGANIZATION	RELEASE DATE
Judy Salazar	CM	05/17/2018

See configuration management system for approval history.

The National Ecological Observatory Network is a project solely funded by the National Science Foundation and managed under cooperative agreement by Battelle. Any opinions, findings, and conclusions or recommendations expressed in this material are those of the author(s) and do not necessarily reflect the views of the National Science Foundation.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Change Record

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
A	03/25/2011	ECO-00148	Initial release
B	01/20/2015	ECO-02273	Production release, template change, method improvements
C	02/26/2015	ECO-02702	Migration to new protocol template
D	1/28/2016	ECO-03547	<p>Major changes to protocol include:</p> <ul style="list-style-type: none"> • All SOPs now implemented together every time protocol is executed, previously SOP D implemented 1X per site • Timing information updated, and preservation of cores prior to core processing eliminated. • Equipment list updates for lab work • SOP C.1 sieving methods updated based on megapit sampling experience • Roots from 2 cores within a clipCell are now pooled <i>after</i> weighing takes place and prior to grinding for chemical analysis / archive. • “other” non-root biomass no longer quantified • Method for calculating core `storageHours` now consistent with Herbaceous Biomass protocol. • Updated Sample Shipment procedure (SOP F) to be consistent with Herbaceous Biomass protocol. • To aid co-locating herbaceous clip and fine root coring, added maps of clip cells within plots to appendix G. • References to mini-rhizotrons removed after descope.
E	02/17/2017	ECO-04403	<ul style="list-style-type: none"> • Added table of common terms and definitions to Section 2.4 • Toxicodendron material condensed and removed when possible, now reference RD[12] • Added ‘Estimated Time’ required for protocol sub-tasks to Section 6.4 based on Field Ops experience. • Updated field and lab equipment list based on feedback from Field Ops prototype. • SOP B: Added ‘Linked Protocol’ call-out box to highlight connection with Herbaceous Biomass.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
			<ul style="list-style-type: none"> • SOP B: Added `coringPossible` to better document sample collection effort, and added `coreDiameter` to allow future changes in equipment. • SOP C: Cores may be soaked overnight prior to wet-seiving. • SOP C: Added instructions for using the wire gauge properly to sort roots by diameter. • SOP C: Simplified pooling instructions, and changed minimum mass of pooled sample from 0.250 g to 0.02 g; removed grinding of samples < 1 g (change from 0.75 g). • SOP C/D: Changed all mass measurement requirements to grams, rather than mix of grams and milligrams. • SOP C/D: Changed timing to allow for overnight pause between SOP C and SOP D. • SOP D: Clarified that `sampleVolume` and `subsampleVolume` can be adjusted on a per core basis to optimize root material mass for sorting. • SOP D: Clarified anticipated effort for sorting root/OM aliquots. • Appendix D: Changed dates from DOY to MM/DD format, and updated Ops-IPT approved missing dates.
F	05/17/2018	ECO-05595	<ul style="list-style-type: none"> • Section 3.1: New section to explicitly call out integration of Belowground Biomass sampling with Herbaceous Clip Harvest. • Section 4.1 and 4.2, Frequency and Timing: Re-organized and simplified to emphasize important scheduling and timing criteria. • Section 6.1, Equipment: Clarified that balances with 0.001 or 0.0001 g accuracy are needed for SOP D; added updated stir-plates or SOP D. • Section 6.4, Estimated Time: Removed labor allocation guidelines, added Table 7 with updated estimated labor per SOP. • SOP B.1: Re-organized workflow to include sample collection method assessment, and added ability to collect a monolith sample type. • SOP B.1: Specified that distance to closest woody stem applies to living stems. • SOP B.2: Split out 'Troubleshooting' into its own section, consistent with Herbaceous Biomass protocol.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
			<ul style="list-style-type: none"> • SOP B.5: New section detailing modified field sampling layout at agricultural sites. • SOP C: Re-wrote wet-sieving procedure based on domain staff feedback. • SOP C.1: Added guidance for clipping branched root systems according to size category. • SOP C.2: Clarified that Oven Start/End Dates/Times are only needed for initial drying, not additional drying after storage. • SOP C.4: Updated text and Table 11 with 40-mesh grinding guidance for C:N analysis subsample. • SOP D: New criteria for selecting soil samples for dilution sampling (spatially balanced approach). • SOP F: Updated to reference digital shipment creation and tracking tools. • Multiple sections: Updated text to reflect digital workflow and mobile app structure. • Multiple sections: Added barcoding workflow required for pooled samples shipped for external analysis; optional for other stages of sample collection and processing. • Added Appendix E: Site-specific modifications necessary to aid with consistent sample collection in D18/19.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

TABLE OF CONTENTS

28 OVERVIEW1

 28.1 Background 1

 28.2 Scope..... 2

 28.2.1 NEON Science Requirements and Data Products 2

 28.3 Acknowledgments..... 2

29 RELATED DOCUMENTS AND ACRONYMS2

 29.1 Applicable Documents 2

 29.2 Reference Documents..... 3

 29.3 Acronyms 3

 29.4 Definitions..... 3

30 METHOD4

 30.1 Integrating Plant Belowground Biomass and Herbaceous Biomass Sampling 7

31 SAMPLING SCHEDULE8

 31.1 Sampling Frequency and Scheduling 8

 31.2 Criteria for Determining Onset of Sampling 10

 31.3 Sampling Timing Contingencies 11

 31.4 Criteria for Reallocation of Sampling Within a Site 11

32 SAFETY12

33 PERSONNEL AND EQUIPMENT.....13

 33.1 Equipment..... 13

 33.2 Training Requirements..... 26

 33.3 Specialized Skills..... 26

 33.4 Estimated Personnel Hours..... 27

34 STANDARD OPERATING PROCEDURES.....28

SOP A PREPARING FOR SAMPLING.....28

 A.1 Sample Labels and Identifiers 28

 A.2 Preparing for soil core sampling in the field (SOP B) 29

 A.3 Preparing for processing soil samples in the laboratory (SOP C)..... 32

 A.4 Preparing for dilution sampling for fine root fragments (SOP D) 32

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

SOP B PLANT BELOWGROUND BIOMASS SOIL SAMPLING IN THE FIELD.....34

B.1 Spatially Linked Protocols 34

B.2 Soil Sample Collection..... 34

B.3 Troubleshooting..... 41

B.4 Sample Preservation 41

B.5 Plant Belowground Biomass at Agricultural Sites 41

SOP C PROCESSING BELOWGROUND BIOMASS SAMPLES IN THE LABORATORY43

C.1 Sieving soil samples for fine root biomass..... 44

C.1.1 44

C.2 Drying, weighing, and processing belowground biomass samples..... 50

C.3 Data Quality Assurance 52

C.4 Grinding and Pooling Biomass for Chemical Analysis and Archive 53

C.5 Equipment maintenance..... 55

SOP D DILUTION SAMPLING FOR FINE ROOT FRAGMENTS56

SOP E DATA ENTRY AND VERIFICATION62

E.1 Digital Data Workflow 62

E.2 Field Datasheets..... 63

E.3 Lab Datasheets..... 63

SOP F SAMPLE SHIPMENT64

F.1 Shipment Preparation Procedure 64

F.2 Laboratory Contact Information and Shipping / Receipt Days 64

35 REFERENCES65

APPENDIX A DATASHEETS66

APPENDIX B QUICK REFERENCES67

B.1 Soil Core Sampling in the Field..... 67

B.2 Processing Belowground Biomass Samples in the Laboratory 67

B.3 Dilution Sampling for Fine Root Fragments..... 68

APPENDIX C REMINDERS69

APPENDIX D ESTIMATED DATES FOR ONSET AND CESSATION OF SAMPLING70

APPENDIX E SITE-SPECIFIC MODIFICATIONS72

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

E.1	D18/19 Site-specific Modifications	72
APPENDIX F	SOIL CORE ASSEMBLY.....	74
APPENDIX G	MANAGING EXPOSURE TO <i>TOXICODENDRON</i> SPECIES.....	75
APPENDIX H	CLIPCELLNUMBER COORDINATES AND MAPS.....	77
H.1	Maps of clipCellNumber by subplotID	77
H.2	Coordinates for clipCellNumbers by subplotID.....	82

LIST OF TABLES AND FIGURES

Table 1.	Definitions for common terms used throughout the Core Sampling for Plant Belowground Biomass protocol.	3
Table 2.	Sampling frequency for plant belowground biomass sampling procedures on a per SOP per plot type basis.	8
Table 3.	Contingency decisions for belowground biomass fine root core sampling.....	11
Table 4.	SOP B equipment list – Sampling plant belowground biomass in the field.....	13
Table 5.	SOP C equipment list – Sieving belowground biomass cores, separating roots from soil organic matter, and drying root samples. Equipment listed is for 3 people working independently at a root washing station.	19
Table 6.	SOP D equipment list – Dilution sampling for fine root biomass fragments < 1 cm	23
Table 7.	Estimated staff and labor hours required for implementation of Plant Belowground Biomass Sampling SOPs.....	27
Table 8.	Soil core bits and the soil types and conditions in which they should be used.....	30
Table 9.	Actions required to prepare equipment and materials for belowground biomass soil sampling in the field (SOP B). Equipment listed here are only those items that require preparation actions before sampling; the full equipment list is provided in Table 4	31
Table 10.	Potential issues encountered during plant Belowground Biomass Core sampling, and issue resolution.	41
Table 11.	Splitting and processing guidelines for fine root samples, based on pooled sample mass.....	54
Table 12.	Datasheets associated with this protocol.....	66
Table 13.	Estimated average dates after which greenness begins to decrease for each NEON site based on MODIS-EVI phenology data. Ideally, soil core sampling and aboveground biomass clip harvests should occur on or near these dates.	70
Table 14.	Summary of site-specific belowground biomass sampling modifications and supporting rationale.....	72
Table 15.	Equipment list – Minimizing exposure to toxic oils from roots of <i>Toxicodendron spp.</i> that may be encountered during plant Belowground Biomass Sampling.	75

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Table 16. List of clipCellNumbers by subplotID and associated easting and northing coordinates. Coordinates correspond to the SW corner of a 0.1m x 2m Clip Strip, and indicate the distance in meters relative to the SW corner of the plot (subplotID = 31) or subplot (subplotID = 21, 23, 39, 41). 82

Figure 1. Illustration of two NEON plot sizes used for plant belowground biomass soil sampling. Grey numbers indicate subplotIDs, and soil sampling is only dependent on subplots for 40m x 40m plots. Italic black numbers show the location of nested subplots that are used for % cover and diversity measurements. Soil sampling is prohibited within 1 m² and 10 m² nested subplots. 5

Figure 2. A 20m x 20m Tower Plot showing the locations of 3.0m x 0.5m clip cells used for plant belowground biomass soil sampling (*left*); the largest 25 m² nested subplot has been omitted for clarity. Within a clip cell selected for soil sampling, one sample is collected from each of the areas to the North and South of the clip-strip (*right*). The red “x” shows the coordinates provided in the Herbaceous Biomass Clip Lists. 6

Figure 3. Workflow for generating unique identifiers for samples, subsamples, etc. for a clip cell from which soils are collected in the field. In the lab, live roots are pooled within a size category, ground, and split into CN and Archive samples, then shipped to external facilities. The amber box indicates samples for which barcodes are required. 28

Figure 4. Assembled plunger used to randomize root fragment samples < 1 cm length as part of dilution sampling (SOP D)..... 33

Figure 5. Delineating the South root sampling area (cross hatched) within a clip “cell” (dashed blue lines) with pin flags. The clip-strip (black lines) lies immediately to the north of the South root sampling area, and the red “x” marks the coordinates provided in the Herbaceous Biomass Clip List. 36

Figure 6. Delineating the North root sampling area with reference to the previously delineated South root sampling area (cross hatched) within a clip “cell” using pin flags (dashed blue lines indicate the clip cell boundary). The middle of both the cell and the clip-strip have been omitted for clarity. 37

Figure 7. Modified clip cell layout when integrating plant belowground biomass sampling and herbaceous biomass clip harvest at agricultural sites. Orange dashes indicate the rotated clip cell. The red flag on the left is placed at the coordinate provided in the Clip List..... 42

Figure 8. Clipping a branched root system to Size Category. The orange bar indicates where two 1-2mm diameter roots are clipped from a ≥ 2mm diameter root; the green bars indicate where 0.5-1mm diameter roots are clipped from larger roots; the blue bars indicate where roots < 0.5mm diameter are clipped from larger roots. The orange circle is not clipped because there are no downstream changes in Size Category; the green circle is not clipped because the fragment is < 1 cm length; the blue circle is not clipped because even though diameter within the circle is < 0.5mm, Size Category is assessed at the largest end, and clipping only occurs at branch points. 46

Figure 9. Ten pairs of labeled aluminum weighing tins for separating roots from OM. Dilution Subsamples are initially transferred to the OM tins via syringe, and roots are then sorted into the ROOT tins. Each tin has a unique Tin ID. 61

Figure 10. Component parts of the Giddings soil core assembly. 74

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

- Figure 11.** Map of clipCellNumbers in a 20m x 20m base plot (subplotID = 31 in provided Clip Lists). Red squares indicate nested subplots used for diversity sampling; clip cells that significantly overlap red squares are not used for fine root soil coring or clip sampling. However, cells with minimal overlap (e.g., 48-54, 68-72, 145-149) do support these sampling activities. 77
- Figure 12.** Map of clipCellNumbers for **subplotID = 21** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling..... 78
- Figure 13.** Map of clipCellNumbers for **subplotID = 23** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling..... 79
- Figure 14.** Map of clipCellNumbers for **subplotID = 39** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling..... 80
- Figure 15.** Map of clipCellNumbers for **subplotID = 41** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling..... 81

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

1 OVERVIEW

1.1 Background

Belowground biomass represents a substantial component of the total plant biomass and plant carbon in terrestrial ecosystems, yet belowground biomass stocks and turnover remain very poorly understood both in space and in time. This is in large part due to the inherent difficulties associated with measuring plant parts that are obscured within soil. Developing a better understanding of how much belowground plant biomass there is, as well as how much of that biomass is produced and decomposed within a given year, is therefore crucial to improving our understanding of how terrestrial ecosystems respond to environmental changes. Here, we define fine roots to be roots with diameter ≤ 10 mm (Burton and Pregitzer 2008). In combination with the belowground biomass soil pit sampling conducted during site construction (RD[09]), the soil core sampling described here will enable estimation of the amount of belowground plant biomass ≤ 10 mm diameter within the same landsurface area from which NEON Tower eddy covariance data are derived; at many sites this will also be the dominant vegetation type(s).

Fine root frequency, biomass, and turnover rates differ substantially across size classes. In general, larger size classes constitute more of the biomass than smaller size classes, but larger roots also turn over much more slowly and therefore contribute less to annual belowground net primary productivity (BNPP) than fine roots do (Steinaker and Wilson 2005, Tierney and Fahey 2007). NEON will employ the most common and robust method to measure belowground biomass in both forest and grassland ecosystems: collection of relatively large diameter (5–10 cm) cores or similarly sized monoliths (Tierney and Fahey 2007, Burton and Pregitzer 2008). Because large coarse roots occur infrequently in the soil, higher volume samples result in more accurate estimates of belowground biomass (Taylor et al. 2013). However, large sample volumes require a significant amount of time to sieve and sort in the laboratory. Given that time is limiting, there is therefore an inherent trade-off between the number and size of samples that must be resolved (Berhongeray et al. 2013). NEON will use a 76.2 mm (3-inch) outside diameter coring device, 66.5 mm (2.6-inch) inside diameter, for belowground biomass sampling, and samples will be cored to 30 cm depth in order to be consistent with the sampling depth used for soil biogeochemistry and microbe sampling (RD[07]). Monolith sampling will be employed when soil conditions prevent collecting a core of sufficient depth (e.g., in rocky soils). Within each clip “cell” selected for belowground biomass sampling, two soil samples will be collected, for a total minimum sample volume of 2722 cm³ per clip cell. If roots up to 10 mm diameter exist at the site, sample volumes of this size should be sufficient to encounter them in the majority of soil samples (Taylor et al. 2013).

To account for differences in BNPP across the spectrum of fine root diameters, researchers typically sort roots within soil samples into various size categories, and then calculate fine root production separately for each size category. Following Burton and Pregitzer (2008), NEON will sort roots within each core or monolith to the following **sizeCategory** bins: < 0.5 mm, 0.5–1 mm, 1–2 mm, and 2–10 mm.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

Soil samples are sieved to remove soil, picked to separate roots from other organic material, and roots are then sorted to diameter size category. Picking and sorting roots is time consuming, and similar to other researchers, NEON will use a 1 cm length cutoff to limit the time spent searching for small root fragments – i.e., root fragments < 1 cm length are ignored and discarded for the majority of cores. However, root fragments < 1 cm length can contribute > 50% of the total root biomass in some ecosystems (Koteen and Baldocchi 2013). To account for the biomass of root fragments < 1 cm length, NEON will employ a dilution technique on a subsample of 20 cores/monoliths every time fine root sampling occurs.

1.2 Scope

This document provides a change-controlled version of Observatory protocols and procedures. Documentation of content changes (i.e. changes in particular tasks or safety practices) will occur via this change-controlled document, not through field manuals or training materials.

1.2.1 NEON Science Requirements and Data Products

This protocol fulfills Observatory science requirements that reside in NEON’s Dynamic Object-Oriented Requirements System (DOORS). Copies of approved science requirements have been exported from DOORS and are available in NEON’s document repository, or upon request.

Execution of this protocol procures samples and/or generates raw data satisfying NEON Observatory scientific requirements. These data and samples are used to create NEON data products, and are documented in the NEON Scientific Data Products Catalog (RD[03]).

1.3 Acknowledgments

The author is grateful for time and detailed advice provided by Daniel Milchunas and Mark Lindquist at the Shortgrass Steppe LTER program. In addition, SOP D “Dilution Sampling for Fine Root Biomass Fragments” is based on the work of Koteen and Baldocchi (2013).

2 RELATED DOCUMENTS AND ACRONYMS

2.1 Applicable Documents

Applicable documents contain higher-level information that is implemented in the current document. Examples include designs, plans, or standards.

AD[01]	NEON.DOC.004300	EHSS Policy, Program and Management Plan
AD[02]	NEON.DOC.004316	Operations Field Safety and Security Manual
AD[03]	NEON.DOC.000724	Domain Chemical Hygiene Plan and Biosafety Manual
AD[04]	NEON.DOC.050005	Field Operations Job Instruction Training Plan
AD[05]	NEON.DOC.000914	NEON Science Design for Plant Biomass and Productivity

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

AD[06]	NEON.DOC.004104	NEON Science Performance QA/QC Plan
--------	-----------------	-------------------------------------

2.2 Reference Documents

Reference documents contain information that supports or complements the current document. Examples include related protocols, datasheets, or general-information references.

RD[01]	NEON.DOC.000008	NEON Acronym List
RD[02]	NEON.DOC.000243	NEON Glossary of Terms
RD[03]	NEON.DOC.002652	NEON Level 1, Level 2 and Level 3 Data Products Catalog
RD[04]	NEON.DOC.001271	AOS/TOS Protocol and Procedure: Data Management
RD[05]	NEON.DOC.002135	Datasheets for TOS Protocol and Procedure: Core Sampling for Plant Belowground Biomass
RD[06]	NEON.DOC.001925	NEON Raw Data Ingest Workbook for TOS Belowground Biomass Soil Sampling
RD[07]	NEON.DOC.014048	TOS Protocol and Procedure: Soil Biogeochemical and Microbial Measurements
RD[08]	NEON.DOC.000987	TOS Protocol and Procedure: Measurement of Vegetation Structure
RD[09]	NEON.DOC.001708	TOS Protocol and Procedure: Soil Pit Sampling for Plant Belowground Biomass
RD[10]	NEON.DOC.001717	TOS Standard Operating Procedure: TruPulse Rangefinder Use and Calibration
RD[11]	NEON.DOC.014037	TOS Protocol and Procedure: Measurement of Herbaceous Biomass
RD[12]	NEON.DOC.001716	TOS Standard Operating Procedure: Toxicodendron Biomass and Handling
RD[13]	NEON.DOC.001710	TOS Protocol and Procedure: Litterfall and Fine Woody Debris
RD[14]	NEON.DOC.001024	TOS Protocol and Procedure: Canopy Foliage Chemistry and Leaf Mass per Area Measurements

2.3 Acronyms

Acronym	Definition
BNPP	Belowground net primary productivity
OM	Organic material

2.4 Definitions

Common terms used throughout this document are defined here, in alphabetical order.

Table 1. Definitions for common terms used throughout the Core Sampling for Plant Belowground Biomass protocol.

Term	Definition
clip cell	A 3.0m x 0.5m rectangular area within a plot that supports plant below-ground biomass sampling; the long-edge of the cell is always oriented north/south.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Term	Definition
clip list	A randomized list of clip cells for each 20m x 20m plot or subplot, provided by NEON Science. Working down the list through time ensures that selected sampling locations will generate an unbiased estimate of plant belowground biomass for every bout.
clip strip	A 2.0m x 0.1m rectangular area, typically centered within each clip cell, that is avoided during plant belowground biomass sampling. Coordinates provided in clip lists correspond to the SW corners of clip strips.
sampling area	Two 0.5m x 0.5m areas that support plant belowground biomass sampling that exist to the north and the south of the clip strip within a given clip cell.
organic material	For the purposes of this protocol, particulate soil organic matter made up of decayed plant parts of unrecognizable origin – i.e., it is not possible to discern leaf, twig, needle, root origin, etc.
residual fraction	The mixture of organic material and root fragments < 1 cm length that is left in the bottom of the sieve after root fragments ≥ 1 cm length have been picked out of the sample. For a subset of soil samples, root fragments in the residual fraction are quantified via the dilution technique.

3 METHOD

The Standard Operating Procedures (SOPs) presented in this protocol describe tasks that, when taken together, allow estimation of plant belowground fine root biomass across four diameter size classes. These SOPs are:

- **SOP A: Preparing for Sampling.** Instructions to prepare for sampling for SOP B, SOP C, and SOP D.
- **SOP B: Plant Belowground Biomass Soil Sampling in the Field.** Collecting soil samples from peak herbaceous biomass clip harvest “cells” in the field, and recording required data and metadata.
- **SOP C: Processing Belowground Biomass Samples in the Laboratory.** Steps to wash, sieve, and separate roots ≥ 1 cm length from mineral soil and organic matter. This SOP also describes steps to dry, weigh, grind, and sub-sample roots for chemical analysis and archive.
- **SOP D: Dilution Sampling for Fine Root Fragments.** A sub-sampling procedure to quantify the amount of fine root biomass present in small root fragments < 1 cm length. By carrying out this SOP, it is possible to ignore root fragments < 1 cm length in SOP C while still generating accurate fine root biomass estimates, resulting in significant time savings.

Plant belowground biomass sampling takes place in 400 m² sampling units located within Tower plots or subplots (**Figure 1**). Soil sampling does not occur in Distributed or Gradient plots. In 20m x 20m Tower plots, two soil samples are collected from one clip “cell” per bout. In larger 40m x 40m Tower plots (i.e. four 400 m² subplots per plot), soil sampling occurs in each of the two subplots randomly assigned by Science Operations for sampling, and two soil samples are collected from one clip cell per subplot per bout. This strategy means that:

- At sites with thirty 20m x 20m Tower plots, there will be a maximum of n=60 soil samples.
- At sites with twenty 40m x 40m Tower plots, there will be a maximum of n=80 soil samples.
- For both plot types, fewer soil samples may be collected if root sampling is not possible in some plots/cells (e.g., due to large roots, rocks, etc.).




Figure 1. Illustration of two NEON plot sizes used for plant belowground biomass soil sampling. Grey numbers indicate subplotIDs, and soil sampling is only dependent on subplots for 40m x 40m plots. Italic black numbers show the location of nested subplots that are used for % cover and diversity measurements. Soil sampling is prohibited within 1 m² and 10 m² nested subplots.

Within each 400 m² plot or subplot, clip cells are 3.0m x 0.5m, and are sequentially numbered (see Appendix H). Coordinates are assigned to the SW corner of a 2.0m x 0.1m clip strip that is centered within each clip cell. These coordinates are relative to the SW corner of the plot or subplot (i.e. the SW corner of the plot or subplot is defined as having coordinates [0,0]) (**Figure 2, left**). To determine soil sampling locations, consult a plot-specific “Clip List” to determine which clip cell was (or will be) used for the peak biomass harvest in the current growing season. Within each clip cell two soil core/monolith samples will be collected: one from each of the areas to the North AND South of the 2.0m x 0.1m clip strip (**Figure 2, right**). To avoid roots and rocks, sampling may occur anywhere within the North and South sampling areas shown in **Figure 2**.




Figure 2. A 20m x 20m Tower Plot showing the locations of 3.0m x 0.5m clip cells used for plant belowground biomass soil sampling (*left*); the largest 25 m² nested subplot has been omitted for clarity. Within a clip cell selected for soil sampling, one sample is collected from each of the areas to the North and South of the clip-strip (*right*). The red “x” shows the coordinates provided in the Herbaceous Biomass Clip Lists.

Prior to collecting a soil sample, crowns, corms, rhizomes, and other perennial belowground parts that are not roots are removed from the top 3 cm of soil and discarded. In some ecosystems, these non-root belowground plant parts may constitute a significant portion of the belowground biomass; however, the NEON protocol is solely focused on measuring fine root biomass.

After sampling from a given clip strip is completed, site hosts may require that holes be backfilled with an approved material (e.g. purchased sand, soil from another site-host approved location, etc.).

Standard Operating Procedures (SOPs), in Section 7 of this document, provide detailed step-by-step directions, contingency plans, sampling tips, and best practices for implementing this sampling procedure. To properly collect and process samples, field staff **must** follow the protocol and associated SOPs. Use NEON’s incident reporting system to resolve any field issues associated with implementing this protocol.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

The value of NEON data hinges on consistent implementation of this protocol across all NEON domains, for the life of the project. It is therefore essential that field personnel carry out this protocol as outlined in this document. In the event that local conditions create uncertainty about carrying out these steps, it is critical that technicians document the problem and enter it in NEON’s incident reporting system.

Quality assurance will be performed on data collected via these procedures according to the NEON Science Performance QA/QC Plan (AD[06]).

3.1 Integrating Plant Belowground Biomass and Herbaceous Biomass Sampling

- In Tower Plots, the Plant Belowground Biomass Sampling protocol and the Herbaceous Biomass protocol (RD[11]) are spatially collocated, and should occur in the same cell in a given sampling year (**Figure 2, right**).
- In an ‘on’ year for plant Belowground Biomass Sampling, the Clip List should indicate whether the Herbaceous Biomass protocol was performed prior to soil sampling. Always attempt to acquire soil samples from the same cell used for clip harvesting.
- When accepting/rejecting cells for potential sampling, be sure to consider suitability and representativeness with respect to **both** protocols.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

4 SAMPLING SCHEDULE

4.1 Sampling Frequency and Scheduling

Sampling Frequency:

Plant Belowground Biomass soil samples are collected according to the schedule in **Table 2**, and implementation of this protocol is scheduled on an inter-annual basis at a given site as part of a suite of synchronized TOS measurements aimed at characterizing plant and soil biogeochemical dynamics.

Synchronized protocols and SOPs include:

- TOS Protocol and Procedure: Soil Biogeochemical and Microbial Sampling, including the N-transformations SOP (RD[07])
- TOS Protocol and Procedure: Litterfall and Fine Woody Debris, litter chemistry component (RD[13])
- TOS Protocol and Procedure: Canopy Foliage Chemistry and Leaf Mass per Area Measurements (RD[14])

Table 2. Sampling frequency for plant belowground biomass sampling procedures on a per SOP per plot type basis.

SOP	Plot Type	Plot Number	Sampling Events	Yearly Interval	Remarks
SOP B	Tower	All	1X per sampling year	5 y	Sampling year is synchronized with protocols listed above.
	Distributed, Gradient	NA	NA	NA	Distributed and Gradient plots are not sampled for plant belowground biomass.
SOP C	Tower	All	1X per sampling year	Same as SOP B	SOP quantifies roots ≥ 1 cm length
SOP D	Tower	All	1X per sampling year	Same as SOP B	Dilution sampling quantifies mass of root fragments < 1 cm length.

Scheduling Considerations:

- **Coordinating with Plant Diversity Sampling:** Plant Belowground Biomass Sampling takes place in all Tower Plots and is collocated with Plant Diversity at the plot scale in a subset of 3 randomly selected Tower Plots.
 - If plant diversity sampling is scheduled to occur prior to plant Belowground Biomass Sampling in a given year, it may be helpful to identify and demarcate a suitable clip cell prior to performing Plant Diversity sampling. This will ensure that the clip cell is not trampled during diversity sampling.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- Should plant Belowground Biomass Sampling occur before Plant Diversity sampling, take care to avoid trampling 1 m² nested subplots used for Plant Diversity % cover measurements.
- **Bout Completion:** A given sampling bout should ideally be concluded within **6 weeks** of initiation so that the belowground standing crop does not change appreciably during the time that all target plots are sampled.
 - This ensures that data collected across all plots within a given sampling bout are as comparable as possible.
- **Field Work and Laboratory Processing:** After soil samples are collected from a given clip strip, the following points are critical with respect to timing:
 - Keep soil samples cold until they are processed in the laboratory. This is because root biomass is biologically active after sampling, and fine root structures are delicate and decompose easily. Samples may be kept cold by:
 - Keeping soil samples in a cooler, kept cold with re-usable cold packs. Cold packs should be exchanged for fresh cold packs every 12 hours. Or,
 - Placing soil samples in a 4–8 °C refrigerator.
 - Process collected soil samples in the laboratory as soon as possible.
 - Ideally, soil samples are processed in the laboratory **within 24 h** of collection.
 - It is acceptable to keep soil cores in cold storage for up to a **maximum of 72 h**.
 - Once laboratory processing is initiated on a given sample, processing should be carried all the way through without stopping.
 - **Scheduling sieving (SOP C) and Dilution Sampling (SOP D):** It is acceptable to pause overnight between execution of SOP C and SOP D.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

4.2 Criteria for Determining Onset of Sampling

It is desirable to perform belowground biomass core sampling when the root crop is at peak biomass. However, peak belowground biomass does not necessarily correspond with peak aboveground biomass, and in some ecosystems, does not vary in a predictable manner within a growing season from year to year (Milchunas and Lauenroth 2001). Combined with the fact that belowground biomass timecourse data are unavailable for the majority of NEON sites, the timing of belowground biomass soil core sampling is guided by these two factors, listed in order of importance:

- **Date of peak biomass herbaceous clip harvest:** Perform belowground biomass soil coring either immediately before, during, or immediately after the herbaceous clip harvest associated with the greatest aboveground *peak biomass*.
 - Site-specific sampling start guidance for Herbaceous Biomass Clip Harvest is derived from the MODIS-EVI satellite product, and is provided in Appendix D of RD[11].
- **Soil moisture:**
 - **Soil hardness:** At some sites, peak herbaceous biomass occurs during hot, dry parts of the year when soils are extremely hard and virtually impenetrable due to high clay content (e.g. D10 CPER). At sites where these conditions occur, the timing of soil core sampling may be moved to earlier in the growing season when soil moisture is more conducive to soil sampling.
 - If soil hardness dictates the timing of sampling, it is not important exactly when in the growing season sampling occurs, but once an acceptable sampling window is chosen for a given site, all future sampling within that site should be initiated within ± 2 weeks of that sampling window.
 - Notify Science staff of the selected sampling start date so that this protocol document may be updated to reflect site-specific sampling dates used for future planning.
 - **Standing water:** At sites where plots may be seasonally submerged (e.g. D03 DSNY), soil sampling must be timed to avoid standing water in potential sampling locations. If a plot is partially submerged but still accessible for terrestrial sampling, “cells” that contain standing water must be rejected for soil sampling, and a new clip-location “cell” must be chosen.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

4.3 Sampling Timing Contingencies

Table 3. Contingency decisions for belowground biomass fine root core sampling.

Delay/ Situation	Action	Outcome for Data Products
Hours	If delay prevents sampling the second core from a given clip cell: <ol style="list-style-type: none"> 1. Bag and label first sampled core, 2. Place labeled bags into a cooler. 3. Resume core sampling in same clip cell ASAP 	None
	If delay occurs between plots or subplots: Resume core sampling ASAP.	
1-14 days	If delay prevents sampling second core from a given clip cell: <ol style="list-style-type: none"> 1. Bag and label first sampled core, 2. Place labeled bags into a cooler. 3. Process first core within 72 hours of sampling. 4. Resume sampling for second core in same clip cell ASAP 	Increased uncertainty in belowground biomass estimates.
	If delay occurs between plots or subplots: <ol style="list-style-type: none"> 1. Process sampled cores within 72 hours. 2. Resume core sampling at additional required plots ASAP. 	
14+ days	If delay prevents sampling second core from a given clip cell: <ol style="list-style-type: none"> 1. Bag and label first sampled core, 2. Place labeled bags into a cooler. 3. Process first core within 72 hours of sampling, 4. Resume core sampling in same clip cell ASAP 	Potentially substantial increases in uncertainty for belowground biomass estimates. If delay prevents completing sampling from all plots or subplots within a 1 month window, belowground biomass may fluctuate substantially.
	If delay occurs between plots or subplots: <ol style="list-style-type: none"> 1. Process sampled cores within 72 hours. 2. Resume core sampling ASAP. 	

4.4 Criteria for Reallocation of Sampling Within a Site

Plant Belowground Biomass Core sampling will occur on the schedule described above at up to 30 Tower Plots per site. Ideally, sampling will occur at these sampling locations for the lifetime of the Observatory (core sites) or the duration of the site’s affiliation with the NEON project (relocatable sites). However, circumstances may arise that require that sampling within a site be shifted from one particular location to another. In general, sampling is considered to be compromised when sampling at a location becomes

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

so limited that data quality is significantly reduced. If sampling at a given plot becomes compromised, a problem ticket should be submitted by Field Operations to Science.

There are two main pathways by which sampling can be compromised. Sampling locations can become inappropriately suited to answer meaningful biological questions (e.g., a terrestrial sampling plot becomes permanently flooded). Alternatively, sampling locations may be located in areas that are logistically impossible to sample on a schedule that that is biologically meaningful.

For plant Belowground Biomass Core sampling, criteria for considering a plot compromised include:

- If sampling cannot be completed in a plot for 2 consecutive bouts.

5 SAFETY

This document identifies procedure-specific safety hazards and associated safety requirements. It does not describe general safety practices or site-specific safety practices.

Personnel working at a NEON site must be compliant with safe field work practices as outlined in the EHSS Policy, Program and Management Plan (AD[01]), and the Operations Field Safety and Security Manual (AD[02]). Additional safety issues associated with this field procedure are outlined below. The Field Operations Manager and the Lead Field Technician have primary authority to stop work activities based on unsafe field conditions; however, all employees have the responsibility and right to stop their work in unsafe conditions.

For the field procedures, safety training is required to properly use the soil corer (e.g., use of heavy gloves and hearing protection). Soils may contain fungi that may cause illness. Refer to the Operations Field Safety and Security Plan (AD[02]) for details on locations and appropriate precautions. In addition, a laser rangefinder/hypsometer/compass instrument may be used to navigate to cells within plots. Safety considerations for this instrument include:

- Avoid staring directly at the laser beam for prolonged periods. The rangefinder is classified as eye-safe to Class 1 limits, which means that virtually no hazard is associated with directly viewing the laser output under normal conditions. As with any laser device, however, reasonable precautions should be taken in its operation. It is recommended that you avoid staring into the transmit aperture while firing the laser.
- Never attempt to view the sun through the scope. Looking at the sun through the scope may permanently damage the eyes.

For the laboratory procedures, safety training is required before operating the grinding mill.

Additional safety issues associated with this field procedure include potential exposure to oils from roots of *Toxicodendron spp.* (discussed in Appendix G, AD[02] and RD[12]).

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

6 PERSONNEL AND EQUIPMENT

6.1 Equipment

The following equipment is needed to implement the procedures in this document. Equipment lists are organized by task. They do not include standard field and laboratory supplies such as charging stations, first aid kits, drying ovens, ultra-low refrigerators, etc.

Table 4. SOP B equipment list – Sampling plant belowground biomass in the field.

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
Durable Items							
		R	Mobile data collection device, tablet or equivalent	Record field sampling metadata	All	Variable	N
Giddings Machine Co.	ST092R	R	Soil core sampling tube, 36" length, 3" OD	Collect soil core sample	All	1	N
Giddings Machine Co.	HS114	R	Soil core drive head assembly	Works with slide hammer to drive soil core tube into soil	All	1	N
Giddings Machine Co.	HS264	R	Soil core drive head pin, 3" length	Attach drive head assembly to core tube	All	2	N
Giddings Machine Co.	ST236	R	Soil core quick relief bit, 3" OD*	Attach to soil core sampling tube	Standard bit for coring most soils	1	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
Giddings Machine Co.	HS304	R	Soil core slide hammer, 16#	Drive sampling tube into soil	All	1	N
Giddings Machine Co.	ST606	R	Soil core basket retainer, 3" adapter	Attach basket retainer system to sampling tube	Sandy soils that do not hold together	1	N
Giddings Machine Co.	ST636	R	Soil core basket retainer, 3" basket	Retain sandy soil in sampling tube	Sandy soils that do not hold together	2	N
Giddings Machine Co.	ST666	R	Soil core basket retainer, 3" bit	Bit that works with basket retainer	Sandy soils that do not hold together	1	N
		S	Toothbrush	Clean soil corer threads in field, if changing bit is required.	Field	2	N
Amazon Cabela's REI	IK270217 895022	S	GPS unit, pre-loaded with plot locations	Navigate to plots or subplots	All	1	N
Forestry Suppliers	91567	R	TruPulse 360R laser rangefinder, current declination entered	Locate clip strip within a plot or subplot	Slope >20%, brushy	1	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
CompassTools Forestry Suppliers	703512 90998	R	Foliage filter for laser rangefinder	Facilitates use of TruPulse in brushy conditions	Brushy vegetation	2	N
		R	Reflective surface (bicycle reflector or reflective tape on back of field notebook/clipboard)	Accurate location of clip strip with TruPulse in "FLT" mode	Used with TruPulse	1	N
		S	Extra battery for TruPulse (CR123A type)	Battery backup	Used with TruPulse	2	N
		R	Fiberglass meter tape (30m or longer)	Locate clip strip within plots or subplots	Plot slope <20%; grassland, savannah	1	N
		R	Hand clippers, fine tip	Remove aboveground plant parts from soil coring location	All	1	N
Ben Meadows Forestry Suppliers	139303 33487	R	Soil knife, hori-hori style	Loosen soil at surface to expose non-root plant parts, and collect monolith sample (when applicable)	All	1	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		R	Large chest-style cooler, with frozen cold packs	Keep core samples cool, slow down root decomposition; one cooler per 8 cores sampled.	All	2+	N
		R	Sharpies	Label paper bags	All	2	N
Ben Meadows	100952	R	Chaining pins, steel	Stretching tapes to enable location of target clip strip	Plot slope <20%; grassland, savannah	2	N
		R	Measuring device, with 1 cm demarcations (e.g., tape, ruler, collapsible measuring stick, etc.)	Measure depth of the litter layer and depth of soil core bore hole	All	1	N
		S	Length of dowel, 1" PVC or equivalent (36" total length)	Push soil core sample out of soil core sampling tube	Soil core sticks to tube	1	N
		S	Heavy duty work gloves	Protect hands during soil core sampling	All	1 pair/person	N
		S	Rubber mallet	Drive soil knife into soil to collect sample.	Monolith sampling	1	N
Consumable items							

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		R	4"x 5" pin flags with PVC stakes	Accurate location of clip strip; PVC stakes avoid magnetic interference with compass or TruPulse	All	6	N
		R	Heavy duty freezer bags, 1.5 or 2 gallon	Store and organize soil core samples	All	40+	N
		S	Hearing protection	Prevent hearing damage from use of slide hammer.	All	As needed	N
		R	Pencils	Record sampling metadata	All	2	N
		R	Waterproof paper, Rite-in-the-Rain or equivalent	Material for making labels to record soil core metadata in the field	All	10+ sheets	N
		R	Clip Lists	Identify clip cell associated with peak biomass clip harvest	All	Varies	N
		R	Random Tower Subplot Lists	Identify subplots for soil core sampling	Tower plots \geq 1600 m ²	Varies	N
RD[05]		R	Belowground biomass "Field Coring Datasheets"	Record sampling metadata	All	Varies	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		S	Horticultural grade sand	Backfill core holes at sites where specified by site host	As specified	4-5 lbs per core	N
		S	Adhesive barcode labels (Type I)	Label samples with barcode readable labels	All	1 sheet	N

R/S=Required/Suggested * Bits with greater relief may be required to prevent soils with high clay content that are prone to expansion from getting stuck in the soil core tube. See <http://www.soilsample.com/tooling/soiltubes.htm> for available bits and soil core accessories.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Table 5. SOP C equipment list – Sieving belowground biomass cores, separating roots from soil organic matter, and drying root samples. Equipment listed is for 3 people working independently at a root washing station.

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
Durable Items							
	MX108866	R	Root washing station	Remove mineral soil from organic material	All	1	N
		S	Plastic bucket, bin, or equivalent (5 gallon, 20 L, etc.)	Soak core sample prior to sieving to break up cohesive clays and rehydrate roots	All	6	N
Fisher	04-881-10G 04-884-1AE	R	Soil sieve, 2 mm stainless mesh, 8” or 12” diameter	Remove mineral soil from organic material	All	6	N
Fisher	04-881-10L 04-884-1AJ	S	Soil sieve, 1 mm stainless mesh, 8” or 12” diameter	Remove mineral soil from organic material	Sandy soil sieving	6	N
Fisher	04-881-10U 04-884-1AS	R	Soil sieve, 250 µm stainless mesh, 8” or 12” diameter	Remove mineral soil from organic material	All	6	N
		S	Rubber or silicone spatula	Transfer soil and roots from bucket to sieve(s).	All	3	N
		R	Rectangular enamel pan or equivalent, white (app. 30 cm x 20 cm, or 13”x 9”)†	Facilitates separating roots (which float) from mineral particles	All	6	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		R	Forceps, blunt tip, stainless steel (e.g., Bioquip 4731, 4732, 4734, 4735)	Separate roots from organic material	All	3	N
		R	* Wire gauge with openings approx. 2mm, 1mm, and 0.5mm	Sort roots into size classes during sieving and picking	All	3	N
		S	Small wire clippers	Clip and separate smaller diameter roots that emerge or fork from bigger roots	Multiple sizeCategories exist	2	N
Thomas Scientific	1711H10	R	Grinding mill, Wiley, 20 mesh	Grind larger fine root sample volumes	Sample masses > 750 mg	1	N
		S	Porcelain mortar, 65 mL capacity, with pestle,	Grind smaller fine root sample volumes, avoid loss of small samples in mill	Sample masses < 750 mg	1 set	N
Fisher	NC9052925	R	Sample microsplitter	Creates identical sub-samples from ground sample	Large root volumes	1	N
Fisher	NC0516918	R	Hi-back pans for sample microsplitter	2 per splitter; receives split sub-sample	With micro splitter	2	N
		R	Sharpie, extra fine tip	Labeling envelopes and scint vials	All	2	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		R	Balance, 0.01 g accuracy or better	Weigh very light root samples	All	1	N
Consumable items							
		R	Pencils	Record dry weight of root samples	All	2	N
RD[05]		R	Lab Weighing Datasheet	Record dry weight of root samples	All	Variable	N
		R	Scintillation vials with caps, 20 mL volume	Containers for ground split sub-samples	All	Variable	N
		R	Large plastic weigh boats	Weigh relatively large quantities of dried root samples	Large root quantities	50+	N
		R	Clasp envelopes, 6"x 9", Kraft paper	Store and organize sieved roots during and after drying	Large root quantities	480-640	N
		R	Coin envelopes, 3 $\frac{3}{8}$ "x6", Kraft paper	Store and organize sieved roots during and after drying	Small root quantities	50	N
		R	Paper bag, 8# Kraft	Organize root samples in the drying ovens	All	20	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Supplier	Supplier Number	R/S	Description	Purpose	Conditions Used	Quantity	Special Handling
		S	Small plastic weigh boats	Weigh relatively small quantities of dried root samples	Small root quantities	50+	N
		R	Adhesive barcode labels (Type I)	Label samples with barcode readable labels	All	1 sheet	N

R/S=Required/Suggested

* Gauge 12 = 2.05 mm, gauge 18 = 1.02 mm, and gauge 24 = 0.51 mm; while not *exactly* the diameters desired, the gauges listed here are acceptable for this protocol.

† Note: the exact dimensions of the pan/tub are not critical, it serves as an aid for more easily spotting roots suspended in water. The only requirement is that it can safely contain liquid; a white material also makes identifying roots easier.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Table 6. SOP D equipment list – Dilution sampling for fine root biomass fragments < 1 cm

Item No.	Supplier Number	R/S	Description	Purpose	Quantity	Special Handling
Durable Items						
Fisher	04-881-10-DD 04-884-1BC	S	Soil sieve, 53 µm stainless mesh, 8” or 12” diameter	Consolidate residual fraction from both samples per clip strip, rinse, and transfer to beaker for dilution	2	N
Fisher	S88857200 S07978S	R	Magnetic mixing plate, stir range 150-2500; or, 50-1500 rpm, minimum 4 x 4 inch stirring surface	Randomize aqueous suspended residual fraction	1	N
		R	Magnetic stir bar, 2” to 3” length	Randomize aqueous suspended residual fraction	2	N
		S	Beaker, 1 L	Hold smaller volumes of aqueous suspended residual fraction	2	N
		S	Beaker, 2 L	Hold large volumes of aqueous suspended residual fraction	2	N
		S	Beaker, 4 L	Hold very large volumes of aqueous suspended residual fraction; e.g., for soils with thick O horizon	2	N
		R	Plunger, diameter approx. 1 cm less than beaker diameter	Stop mixing vortex, randomize aqueous suspended residual fraction	1 per per beaker size	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Item No.	Supplier Number	R/S	Description	Purpose	Quantity	Special Handling
		R	Syringe, 40 – 60 mL, with tip cut off to make a 1 cm diameter aperture	Aspirate sub-sample from randomized aqueous residual fraction	2	N
		R	Plastic laboratory squirt bottle, filled with water	Rinse syringe following sub-sampling	1	N
		R	Aluminum weighing dishes, 65 mL (e.g. Fisher #: 08-732-102)	Hold and dry root and organic material from sub-samples.	200	N
		R	Forceps, fine tip	Pick small root fragments apart from organic material	2	N
		S	Heavy duty sheet tray, baking or equivalent	Transfer aqueous samples in aluminum dishes to drying ovens; hold and protect samples throughout oven drying procedure.	1	N
		R	Balance, 0.001 g or 0.0001 g (preferred) accuracy	Weigh extremely light dried dilution samples	1	N
		R	Threaded rod or bolt, long enough to fit beaker. 1/4 " diameter recommended	Plunger device for dilution sampling, rod	1	N
		R	Semi-rigid or rigid waterproof material (e.g., vinyl laminate wall base moulding, polycarbonate), circular cut-out, with diameter ~1cm less than beaker diameter	Plunger device for dilution sampling, plunger base	1	N

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Item No.	Supplier Number	R/S	Description	Purpose	Quantity	Special Handling
		S	Wood Dowel, 12" by 3/4" diameter, optional	Plunger device for dilution sampling, plunger handle	1	N
		R	Hex Nuts, 1/4" (or whatever diameter fits your threaded rod)	Plunger device for dilution sampling, fastening	4	N
Consumable Items						
		R	Distilled or filtered water (18.2 MOhm not required, lesser purity acceptable)	Suspend residual fraction for dilution method; avoid mineral build-up on weighing tins used for very light samples	As needed	N

R/S=Required/Suggested

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

6.2 Training Requirements

All technicians must complete required safety training and protocol-specific training for safety and implementation of this protocol as required in Field Operations Job Instruction Training Plan (AD[04]).

For the field component of this protocol, technicians must be trained in navigating to points in the field with a GPS and manual methods. Most critically, technicians must be trained to quickly identify commonly encountered types of belowground plant parts at the sites within the region of employment (e.g. crowns, corms, rhizomes, roots, etc.).



Training for both the field and laboratory work must emphasize the importance of consistent, detailed labeling and barcoding of all samples. ***Improper or inconsistent labeling is the most common and problematic error associated with this work!***

6.3 Specialized Skills

For the field work, a minimum of 2 field technicians are required for harvesting soil cores due to weight of equipment and soil cores. When perennial grasses are present, technicians must possess a demonstrated ability to identify crown material associated with these plants.

For the laboratory work, technicians are required to wash, dry, weigh, grind, and sub-sample belowground biomass samples for shipment to external analytical or archive facilities.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

6.4 Estimated Personnel Hours

The time required to implement a protocol will vary depending on a number of factors, such as skill level, system diversity, environmental conditions, and distance between sample plots. The timeframe provided below is an estimate based on completion of a task by a skilled two-person team (i.e., not the time it takes at the beginning of the field season). Use this estimate as framework for assessing progress. If a task is taking significantly longer than the estimated time, an incident should be reported.

Table 7. Estimated staff and labor hours required for implementation of Plant Belowground Biomass Sampling SOPs.

SOP	Estimated time	Suggested staff	Total person hours
SOP A.1: Preparing for soil core sampling in the field	1 h	1	1 h
SOP A.2: Preparing for processing soil cores in the lab	0.5 h	1	0.5 h
SOP A.3: Preparing for dilution sampling	4-6 h (first sampling) 0.5 h (subsequently)	1	4-6 h (first sampling) 0.5 h (subsequent)
SOP B: Soil sampling in the field	1 h per plot (20m x 20m) 2 h per plot (40m x 40m)	2	2 h per plot (20m x 20m) 4 h per plot (40m x 40m)
SOP C.1: Processing samples in the laboratory	1 h per core (sieving) 1-3 h per core (sorting)	1 per core	2-4 h per core
SOP C.2 and C.3: Drying, weighing and QA	8 h per bout (initial) 1 h per bout (QA weigh)	1 (initial) 1 (QA weigh)	8 h per bout (initial) 1 h per bout (QA weigh)
SOP C.4: Grinding for external analysis	8 h per bout	1	8 h per bout
SOP D: Dilution sampling	3 h per core	1 per core	3 h per core
SOP E: Data Entry and Verification	TBD per bout	2	TBD per bout
SOP F: Sample shipment	1-2 h per bout	1	1-2 h per bout

7 STANDARD OPERATING PROCEDURES

SOP A Preparing for Sampling

A.1 Sample Labels and Identifiers

By default, each soil core or monolith collected in the field is assigned a sampleID, and roots sorted from a sample are assigned subsampleIDs. For grinding, chemical analysis and archive, subsamples are combined to create a pooled sample that is assigned a poolSampleID, and the pooled sample is then split for chemical analysis (assigned a cnSampleID), and biogeochemistry archive (assigned a bgcArchiveID)(see **Figure 3**).




Figure 3. Workflow for generating unique identifiers for samples, subsamples, etc. for a clip cell from which soils are collected in the field. In the lab, live roots are pooled within a size category, ground, and split into CN and Archive samples, then shipped to external facilities. The amber box indicates samples for which barcodes are required.

- Samples, subsamples, pooled samples, and CN and Archive samples shown in **Figure 3** are labeled with location, date, and other information required to uniquely identify the sample.
- In addition to labeling samples with human readable information, samples, subsamples, etc. may also be associated with an optional scannable barcode.
 - Use of barcodes throughout this procedure greatly enhances speed and accuracy of selecting the correct sampleID throughout the data entry process.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

A.1.1 Barcode Workflow

- Barcodes are required for CN samples and Archive samples (**Figure 3**); the shipping workflow depends on barcodes.
 - Until they are linked with a subsample, barcodes do not contain information specific to sample provenance.
- Barcodes are optional at this time for other samples, subsamples and pooled samples.
 - Barcodes may improve sample tracking, and reduce transcription errors associated with writing sample and subsample identifiers by hand.
 - Barcodes may also speed entry of data into mobile applications.

If using barcodes:

- Adhesive barcode labels should be applied to dry, room temperature bags, envelopes or sample containers at least 30 minutes in advance of their use. Barcodes may also be applied at the start of the season.
- Barcodes are unique, but are not initially associated with a particular sample; if using barcodes, it is encouraged to apply these in advance.
- See Section 6.1 for the appropriate barcode label type for these procedures. Note that a barcode label is applied *in addition to* labeling the subsample with human-readable information (hand-written or printed).

Barcodes are scanned into the mobile application when indicated in the protocol; only one barcode may be associated with a particular sample, subsample, etc.. Do not reuse barcodes. If a barcode is associated with multiple subsamples, the data ingest system will throw an error and refuse to pull in entered data.

A.2 Preparing for soil core sampling in the field (SOP B)

1. Make waterproof labels for tracking soil sampling metadata in the field.
 - Cut waterproof paper (Rite-in-the-Rain or equivalent) into approx. 3”x 5” rectangles.
 - *Optional:* Affix a Type I barcode to each rectangle, to be associated with the sampleID in the field.
 - Write metadata on the labels with Sharpie in the field, and place the labels inside the plastic bags with the soil samples.
 - The outside of plastic bags may also be labeled with Sharpie for easy visibility, but do **NOT** rely only on labeling the outside of bags; Sharpie can smear and become unreadable.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

2. If it is possible to collect soil cores: Use local knowledge of the soils present at the site, and determine the type of soil coring bit that is required for the soil conditions at the site (i.e. the degree of relief needed inside the bit) (**Table 8**).

Table 8. Soil core bits and the soil types and conditions in which they should be used.

Bit Type	Intended Soil Conditions or Soil Type
Standard taper	Dry soils
Quick relief	Clay/Loam soils (i.e. “typical soils”); relief inside bit allows for moderate expansion of core inside soil core tube, prevents sample from getting stuck
Heavy duty quick relief	Heavy clay soils; additional relief allows for additional expansion of core inside soil core tube
Extra heavy duty quick relief	Extra heavy expansive clay soils; allows for maximal expansion of core inside soil core tube
Basket retainer bit	Works with basket retainer and basket retainer adapter to retain sandy, non-cohesive soil samples inside the soil core tube

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

3. Prepare equipment and material according to **Table 9** below.

Table 9. Actions required to prepare equipment and materials for belowground biomass soil sampling in the field (SOP B). Equipment listed here are only those items that require preparation actions before sampling; the full equipment list is provided in **Table 4**.

Item Description	Action(s)
Mobile data collection device	<ul style="list-style-type: none"> • Charge and sync
GPS unit	<ul style="list-style-type: none"> • Charge • Load target plot locations
Compass, mirror-sight, adjustable declination	Check/set correct declination*
TruPulse 360R laser rangefinder and clinometer	<ul style="list-style-type: none"> • Check battery, charge (if possible) • Clean lenses with lens cloth or lens tissue (if necessary) • Check/set correct declination*. See RD[10]. • Calibrate tilt-sensor (only necessary after severe drop-shock; see RD[10]).
76.2mm OD (66.5mm ID) soil core tube and bit assembly	Measure 30 cm from the bottom of the bit, and mark on the tube with electrical tape.
Re-usable cold packs	Place in -20 °C freezer
Hand clippers	Clean and sharpen blades (if necessary)
Sand, or other site-specific material	Check with the site host to determine the desired back-fill material. Ensure supply is sufficient for backfilling soil core holes.
Belowground biomass “Field Sampling Datasheet”	Print as needed on waterproof copy paper; needed for backup in the event digital data collection workflow fails.
Clip Lists	Sync with tablet or print as needed on waterproof copy paper
Tower Plot “Random Subplot List”	Sync with tablet or print as needed on waterproof copy paper; only needed for 40m x 40m Tower Plots.

* Declination changes with time and should be looked up annually per site: <http://www.ngdc.noaa.gov/geomag-web/>

A.2.1 Integrating Belowground Biomass Sampling with Clip Harvest in Agricultural Plots

1. For densely planted, tall-stature crops such as corn, delineate plant belowground biomass sampling areas and the clip strip well before crop maturity. Delineation of sampling areas will be difficult once crops are taller than breast height.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

A.3 Preparing for processing soil samples in the laboratory (SOP C)

1. Empty and clean root washing station sediment traps.
2. Prepare drying oven for drying root samples.
 - a. Set oven temperature to 65°C.
 - b. Clear necessary space.
3. Prepare barcodes:
 - a. *Optional:* Affix Type I barcodes to coin envelopes used to dry roots. A minimum of one root envelope per soil sample must be barcoded to enable functionality.
 - b. *Required:* Affix Type I barcodes length-wise to 20 mL plastic scint vials. Do not wrap barcode around the vials; curved surfaces prevent accurate reading of barcodes.
4. Print lab weighing datasheets (optional, only if data are not entered directly into digital workflow).

A.4 Preparing for dilution sampling for fine root fragments (SOP D)

Item Description	Action(s)
Dilution Sampling Plunger	<ul style="list-style-type: none"> • Assemble plunger from items listed in Table 6.

1. Assemble a plunger (**Figure 4**), with diameter suitable for the size of beaker selected from **Table 6**; plunger pieces can be assembled from locally available hardware store parts.
 - a. Use scissors, a utility knife, or other appropriate tool to cut a circular section out of a piece of acrylic, polycarbonate, or vinyl. The diameter of the circle should be approx. 1 cm less than the diameter of the beaker.
 - b. Create a small hole in the center of the circle just large enough to fit the threaded rod zinc rod through (hole is approx. ¼”).
 - c. Tighten on one nut <1” from the bottom. Then slide the cut disk on, and fasten with another nut.
 - d. Drill a ¼” hole completely through the wooden dowel and cut length to a preferred size.
 - e. Repeat step 3 to attach the dowel using two nuts.
 - f. Coat the nut and tip of the zinc rod at the ‘circle’ end with silicone to avoid breaking the bottom of the beaker when plunging.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F




Figure 4. Assembled plunger used to randomize root fragment samples < 1 cm length as part of dilution sampling (SOP D).

2. Label aluminum weigh tins with unique Tin IDs.
3. Print lab dilution datasheets as necessary (skip if using digital workflow).

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

SOP B Plant Belowground Biomass Soil Sampling in the Field

Goals

- Collect two plant belowground biomass soil samples per clip cell.
- Keep soil samples cold until they are processed in the laboratory.
- Collect required field sampling metadata.
 - The preferred method for data collection is the Belowground Biomass Field mobile application.
 - The Belowground Biomass Sampling Fulcrum Manual on the SSL contains detailed data entry instructions.

B.1 Spatially Linked Protocols

Herbaceous Clip Harvest

- If plant Belowground Biomass sampling is scheduled prior to Herbaceous Biomass clip harvest sampling, accepting/rejecting clip strips must be done with both protocols in mind.
 - It is highly desirable for accepted clip strips to support both protocols.
- If Herbaceous Biomass sampling is scheduled before plant Belowground Biomass sampling:
 - Consult each per plot Clip List to enable co-location of sampling within cells in each plot.
 - Stagger the sampling activities to ensure sufficient oven space for all samples.
- At Agricultural sites:
 - Tall-stature crops may require pre-delineation of sampling areas (SOP A.2).
 - Additional steps are required to ensure that soil sampling areas and agricultural clip strips do not overlap (SOP B.5).

Plant Diversity

- Plant Diversity sampling occurs in 3 randomly selected Tower Plots each year. In these plots, identify and demarcate a suitable clip strip for plant belowground biomass/herbaceous biomass sampling prior to performing Plant Diversity sampling.
- This will ensure that the clip strip is not trampled during Plant Diversity sampling.

B.2 Soil Sample Collection

1. Navigate to the plot or subplot to be sampled.
2. Use the plot or subplot-specific Clip List to identify the clip cell that was (or will be) used for the peak herbaceous biomass clip harvest in the current year.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- If the site host allows, a pin flag may be left behind at the SW corner of the clip strip to aid collocation across protocols.
 - The Clip List provides the randomized list of potential clip cells per plot or subplot.
 - Coordinates provided for each clip cell correspond to the SW corner of the clip-strip – i.e. the area from which herbaceous biomass is harvested (**Figure 2**).
 - The Clip List indicates which clip cells have already been harvested or rejected; on the Clip List, mark cells selected for Plant Belowground Biomass Sampling with **status = 5**.
 - If the desired peak biomass clip cell is submerged by standing water, reject and work down the Clip List to choose an acceptable clip cell, and record “peak biomass cell submerged” in the “remarks” field.
3. Locate the relative offsetEasting and offsetNorthing coordinates of the SW corner of the clip-strip within the target clip “cell”. The procedure used to locate the offsetEasting coordinate depends on the value of the relative offsetNorthing coordinate:

If the ‘offsetNorthing’ coordinate is < 10:

- a. Run a tape East/West along the south edge of the plot or subplot between the (0,0) → (20,0) plot markers (**Figure 2**), and stretch the tape taut.*
- b. Place a pin flag at the desired relative X-coordinate.
- c. Standing directly over the pin flag that was just placed, use the TruPulse in **HD** mode with a reflective surface to locate the Y-coordinate.
 - Make sure the azimuth is 0° (True North) when shooting the TruPulse to find the Y-coordinate (see RD[10] for detailed instructions for operating the TruPulse).
- d. Place a pin flag at the clip-strip (X,Y) location – i.e. the SW corner of the clip-strip.

If the ‘offsetNorthing’ coordinate is > 10:

- a. Run a tape* East/West from the plot or subplot centroid (10,10) to either the (0,10) position or the (20,10) position (**Figure 2**).

offsetEasting coordinate	Tape Layout ¹
1 < X < 10	From (10,10) → (0,10)
10 < X < 20	From (10,10) → (20,10)

¹ Use the TruPulse in **AZ** mode to guide the tape along the correct azimuth.

- b. Place a pin flag at the desired relative offsetEasting coordinate.
- c. Standing directly over the pin flag that was just placed, use the TruPulse in **HD** mode with a reflective surface to locate the Y-coordinate.
 - Make sure the azimuth is 0° (True North) when shooting the TruPulse to find the Y-coordinate (see RD[10] for detailed instructions for operating the TruPulse).
- d. Place a pin flag at the SW corner of the Clip Strip.

TIPS



- If the plot slope is > 20%, or there is significant brush or obstacles that prevent accurately stretching a tape, the TruPulse laser rangefinder must be used in **HD** mode to place the initial pin flags relative to the plot markers.
- Plot slope can be quickly estimated using the inclinometer in the TruPulse (**INC** mode).

4. Assess whether the clip cell is representative of the plot, and accept or reject the location.

Remember that you must consider both this protocol, and the Herbaceous Biomass protocol.

- See Figure 3 in SOP B of RD[11] for detailed acceptance/rejection criteria.
 - Obstacles, disturbances, and/or irregularities on the surface may lead to a cell being unrepresentative, and these may include trees, large rocks, ant nests, downed logs, etc.
 - If > 3 consecutive potential cells are rejected as ‘unrepresentative,’ it is necessary to recalibrate the working definition of ‘representative.’
5. Mark the four corners of the South root sampling area within the clip strip “cell” to delineate where the first of the two soil samples should be collected (**Figure 5**). Pin flags, a 50cm x 50cm PVC frame, or equivalent can be employed for this purpose. If using pin flags:
 - a. Place pin flag “A” 20 cm to the west of the coordinates provided in the Clip List (i.e. the red “x” in **Figure 5**) – use a meter tape or ruler to be accurate.
 - b. Place pin flag “B” 50 cm to the east of pin flag “A”
 - c. Place pin flag “C” 50 cm to the south of pin flag “A”
 - d. Place pin flag “D” 50 cm to the south of pin flag “B”




Figure 5. Delineating the South root sampling area (cross hatched) within a clip “cell” (dashed blue lines) with pin flags. The clip-strip (black lines) lies immediately to the north of the South root sampling area, and the red “x” marks the coordinates provided in the Herbaceous Biomass Clip List.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

6. Mark the four corners of the North root sampling area within the clip strip “cell” to delineate where the second of the two soil samples should be collected (**Figure 6**). Pin flags, PVC frame, or equivalent may be employed. If using pin flags:
 - a. Place pin flag “E” 2 m to the north of pin flag “A”
 - b. Place pin flag “F” 2.5 m to the north of pin flag “A”
 - c. Place pin flag “G” 2 m to the north of pin flag “B”
 - d. Place pin flag “H” 2.5 m to the north of pin flag “B”




Figure 6. Delineating the North root sampling area with reference to the previously delineated South root sampling area (cross hatched) within a clip “cell” using pin flags (dashed blue lines indicate the clip cell boundary). The middle of both the cell and the clip-strip have been omitted for clarity.

7. Within one of the targeted root sampling areas, identify the exact location from which the soil sample will be collected, and determine the **Root Sampling Method** (‘core’ or ‘monolith’).
 - a. To avoid rocks and roots that may interfere with coring, probe the ground within the target sampling area with a chaining pin to determine a suitable location.
 - b. If it appears possible to collect a sample to 30 cm:
 - i. Assemble the soil core tube, bit, retainer basket (if necessary), and drive head (see Appendix E), and prepare to collect a **soil core sample**.
 - ii. Note that the corer will handle infrequent smaller diameter rocks (2-5 cm diameter), but cannot handle rocks of this size when they are abundant.
 - iii. You will develop site-specific intuition as to when probing indicates coring is possible.
 - c. If collecting a sample to 30 cm depth appears impossible – i.e., probing reveals there is no place within the target coring area where the corer could be inserted without encountering obstacles before reaching 30 cm depth:

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- i. Prepare to collect a **soil monolith sample** (10cm x 10cm surface area, 30 cm target depth).
 - ii. Note that the soil corer can reliably cut through roots up to 1 cm diameter and larger. If you encounter roots of this size, coring is still the preferred collection method.

8. If it is **NOT** possible to collect a soil sample from a clip cell soil sampling area, AND the clip cell is deemed representative of the plot, follow (a) and (b) below, otherwise proceed to the next step.
 - a. Use the tablet to create a record for the **Plot ID** and **Clip Cell Number**, and create a child-record to record the 'Core Field Data' for the appropriate sampling area ('North' or 'South').
 - b. Select **Root Sampling Possible** = 'No', and save the child record.
 - c. Return to step (7) above, and attempt to collect a sample from the remaining soil sampling area within the clip cell.

9. Create a label on waterproof paper with the information below. The label and the soil sample will then be placed in a large plastic freezer bag.
 - **Collect Date**, YYYYMMDD format
 - **Plot ID** and **Subplot ID**,
for 20m x 20m plots, subplotID = 31
for 40m x 40m plots, subplotID = 21, 23, 39, or 41
 - **Clip Cell Number**, the 3 digits to the right of the last "_" in the clipID on the Clip List
 - **Core ID**, *North* or *South*

10. Remove plants and litter from the sampling area, then remove non-root belowground plant parts from the top 3 cm of soil:
 - a. Use hand clippers to remove aboveground plant leaves and stems from the exact area from which a sample will be collected, and remove litter down to the soil surface.
 - b. Score the ground with the soil core bit or soil knife so it is clear exactly where the soil sample will be collected.
 - c. Loosen the soil with a soil knife, and remove the soil from around any perennial non-root plant parts growing within the scored area (e.g. corms, rhizomes, crowns, biological soil crust, etc.).
 - If perennial graminoid crowns are present, remove soil until the transition from crown to root is visible.
 - If biological soil crust is present, score the soil just below the moss/lichen layer and carefully remove the crust. The crust can be placed back over the coring hole on top of the backfill material.
 - d. Clip all *non-root* material from within the scored area, and discard.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

11. Collect a soil sample to 30 cm maximum depth:

If using the **core** sampling method:

- a. Position the soil core bit back over the scored area, and make sure the soil core assembly is vertical. If the plot is sloped, the soil core assembly should still be vertical.
- b. Use the slide hammer to pound the soil core tube to 30 cm maximum depth (*which should be marked on the soil core tube with electrical tape or similar*).



Once the soil corer is in the ground, do not turn the unit counter-clockwise, as this will unscrew the bit from the core tube underground, resulting in loss of the bit.

- c. Push the core tube back and forth sharply several times to loosen it within the soil profile.
- d. Remove the core tube from the ground, carefully extract the core into a plastic bag, and place the label inside the bag.

If using the **monolith** sampling method:

- a. Use the soil knife and a ruler to measure and cut a sample with 10cm x 10cm surface area. Use a rubber mallet to drive the soil knife vertically (if necessary).
- b. Cut and remove soil sample as you work, and place into a plastic bag with a label inside.
 - i. When rocks are encountered, remove when possible.
 - ii. Removal of larger rocks may enlarge the hole. This is acceptable, but soil sample should only be collected from the target 10cm x 10cm area as it extends downward from the surface. The intent is to enable calculation of root density (g cm^{-3}) and root mass per area (g m^{-2}).
- c. Collect soil and roots from the 10cm x 10cm sampling area down to a maximum depth of 30 cm.
 - i. See **Table 10** if a sampling depth of 30 cm cannot be attained.

12. Use the tablet to create a record in the Belowground Biomass Field app for the sampled **Plot ID** and **Clip Cell Number**, and enter required **Clip Cell** sampling information:

- **Plot ID**; select from the site-specific drop-down list; if using paper data sheets use *SITE_###* format.
- **Subplot ID**; for 20m x 20m Tower Plots, subplotID = 31. For 40m x 40m Tower Plots, subplotID = 21, 23, 39 or 41.
- **Sampling Protocol Version**; select the version of the protocol used for sampling, typically the current released version.
- **Collect Date/Time**; use *YYYYMMDD* and *HH:mm* 24-h time format. Time is the **local** time the sample was placed in the cooler after collection.
- **Clip Cell Number**; *###* format. This number is the last 3 digits of the clipID from the Clip List.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

13. Create a child record for the **Core ID** (*North* or *South*), and measure and enter the required sampling data.

a. Obtain the dimensions of the hole from which the sample was collected:

If using the **core** sampling method:

- i. **Core Diameter**; measure the inside diameter of the coring device, nearest 0.05 cm. For the standard corer listed in Section 6.1, the value is 6.65 cm.
- ii. **Root Sample Depth**; measure the average depth below the surface to which the soil sample was collected, nearest 1 cm.
 - Push past any loose soil that fell back into the hole, and measure a representative depth.

If using the **monolith** sampling method:

- i. **Monolith Length** and **Monolith Width**; the actual length and width of the 10cm x 10cm surface area from which the sample was collected, nearest 1 cm.
 - Dimensions may be recorded to the nearest 0.1 cm, if possible.
 - ii. **Root Sample Depth**; measure the average depth below the surface to which the soil sample was collected, nearest 1 cm, as above for **core** sampling.
- b. **Litter Depth**; average litter depth for the entire ‘North’ or ‘South’ soil sampling area, nearest 1 cm.
- If litter is < 1 cm average depth, record 0.5 cm.
- c. **Woody Stem Distance, DBH ≥ 10 cm**; distance to closest *living* woody stem with DBH ≥ 10 cm, nearest 0.1 m.
- d. **Woody Stem Distance, DBH ≥ 1 cm**; distance to closest *living* woody stem with 1 cm ≤ DBH < 10 cm, nearest 0.1 m.
- e. **Bare Ground**; % of entire ‘North’ or ‘South’ soil sampling area that is made up of soil (particles < 5 mm diameter) and/or rock (mineral particles > 5 mm diameter), nearest 10%.
- f. **Sample Barcode** (optional); scan in the sample barcode affixed to the waterproof label.
- g. Save the child record.

14. Place the sample label in the bag, seal, and place the bagged soil sample into cold storage. Maintain cold until samples can be processed in the laboratory.

- Refresh cold packs every 12 h or transfer cores to a refrigerator in the lab.

15. Backfill the sample hole with site-host approved material (if required by site host).

16. Return to step (7) and collect an additional sample from the remaining ‘North’ or ‘South’ sampling area within the clip cell.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- Once two samples per clipID have been collected, save the parent record for the clipID, and proceed to the next clipID on the list.

B.3 Troubleshooting

Table 10. Potential issues encountered during plant Belowground Biomass Core sampling, and issue resolution.

Issue	Resolution
30 cm depth not reached due to obstacles	<ul style="list-style-type: none"> Attempt sample collection at up to 3 total locations within the target coring area. Collect a sample to the greatest depth possible. Record the final sampling depth.
A sample cannot be collected from a representative sampling area	<ul style="list-style-type: none"> Record Root Sampling Possible = 'No' Move on to the next sampling area within the clip cell, the next clipID or the next plotID, whichever is applicable.

B.4 Sample Preservation

- Keep samples in a cooler with cold packs to minimize cellular activity, reduce decomposition, and preserve sample mass.
- Change cold packs for fresh ones every 12 h or transfer to a 4-8 °C refrigerator prior to laboratory processing.
- Soil cores must be processed in the laboratory **within 72 h** of sampling in the field.

IMPORTANT: Record the **Collect Date** and **time** in the Field app AND **Oven Start Date** and **time** in the Lab Weighing app so that the number of hours the samples were stored cold can be calculated.

B.5 Plant Belowground Biomass at Agricultural Sites

Delineation and flagging of sampling areas for both Plant Belowground Biomass Sampling and the Agricultural Biomass SOP should be carried out at the same time regardless of which protocol is executed first.

- Bring a 3 m long folding ruler, or equivalent rigid measuring device, and 0.5m x 0.5m frames used to lay out the belowground biomass sampling areas.
- Locate the SW corner of the clip strip as in SOP B.2. At agricultural sites, *this Clip List coordinate will serve as the SW corner of the clip cell rather than the clip strip.*
- Rotate clockwise until you are facing perpendicular to crop rows (**Figure 7**).
- Use the rigid measuring stick to lay out the 3 m long left side of a 3.0m x 0.5m clip cell.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

5. Use the 0.5m x 0.5m frames to layout the plant belowground biomass sampling areas at either end of the clip cell. Flag the lower-left corner of the cell and the upper-right corner of the cell.
 - a. Flagging should remain if soil sampling occurs prior to agricultural clip harvest.
6. Delineate a clip strip of the appropriate dimensions; the long edge of the clip strip should remain perpendicular to crop rows (**Figure 7**).




Figure 7. Modified clip cell layout when integrating plant belowground biomass sampling and herbaceous biomass clip harvest at agricultural sites. Orange dashes indicate the rotated clip cell. The red flag on the left is placed at the coordinate provided in the Clip List.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

SOP C Processing Belowground Biomass Samples in the Laboratory

Goals

- Isolate fine roots from soil, sort to **Size Category** and **Root Status**, then dry and weigh.
- For live roots, grind dried biomass and ship to external facilities for chemical analysis and bioarchive (latter only if sufficient sample).
- Collect required laboratory data.
 - The preferred methods for data collection are the Belowground Biomass Lab Weighing and Belowground Biomass Grind and Pool mobile applications.
 - The Belowground Biomass Sampling Fulcrum Manual on the SSL contains detailed data entry instructions.

Gloves

Fine root samples generated from this procedure are analyzed for isotopes (¹³C and ¹⁵N); as such, disposable latex or nitrile gloves are required during sieving, sorting, and grinding tasks to prevent contamination of the sample with your hands.

Overview

Use time estimates for lab processing steps provided in Section 6.4 to plan field work so that a backlog of cores does not develop, and the **72 h maximum cold storage** requirement can be met. Time sensitive processing steps include:

1. Determine whether soil samples will be wet-sieved or dry-sieved.
 - **Wet-sieving:** If the soil samples have a large amount of root mass, soils are finely textured, or the soil is difficult to break apart by hand without fragmenting roots, wet-sieving may be the most efficient procedure for separating roots from soil.
 - Soak hard and/or clay-rich soil samples for 1-12 h before wet-sieving.
 - **Dry-sieving:** If the soil samples have little root mass and are coarsely textured, or soils are coarsely textured and the roots are very brittle, dry-sieving soils may be the most efficient procedure.
2. Wash and sieve soil cores to separate mineral soil from root biomass and organic matter, and separate roots ≥ 1 cm length from the residual fraction.
3. Set aside the residual fraction from a random subset of 20 samples for processing with SOP D.
 - See SOP D, step (1) for guidance on randomly selecting samples for dilution sampling.
 - It is acceptable to pause overnight between execution of SOP C and SOP D. Store labeled residual fractions overnight at 4 °C in a sealed container (e.g., labeled 50 mL tube).
4. Dry fine root biomass ≥ 1 cm length to constant weight.



Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Once roots are dry, time is no longer of the essence, and the following may be completed as time allows:

5. Weigh and record dry weight biomass.
6. Grind fine root samples for chemical analyses.

C.1 Sieving soil samples for fine root biomass

C.1.1 Wet Sieving Soils

1. For wet sieving:
 - For hard, dry and/or clay-rich soils: Soak the sample in water for a minimum of 1 hour in a 5 gallon plastic bucket, or appropriately sized container, to facilitate breaking up the sample. Water depth should be sufficient to cover the soil.
 - Soil samples may also soak overnight in the bucket to facilitate workflow scheduling.
 - **Optional Soil Sample Barcodes** (from the field): Retain the barcode and group with downstream root subsamples when they are placed in the oven for drying.
2. For each soil sample, label up to 8 coin envelopes with the information below. The total number needed depends on the number of **Root Status** x **Size Category** combinations in the sample. For large amount of root biomass within a given size class, use a clasp envelope instead.

Optional Root Subsample Barcodes: A minimum of one root envelope per soil sample may be pre-labeled with a Type I barcode, in addition to human-readable information.

- **Collect Date**, date roots were sampled in the field; YYYYMMDD format
 - **Plot ID** and **Subplot ID**,
 for 20m x 20m plots, subplotID = 31;
 for 40m x 40m plots, subplotID = 21, 23, 39, or 41
 - **Clip Cell Number**, the 3 digits to the right of the last “_” in the clipID on the Clip List
 - **Core ID**, either ‘North’ or ‘South’
 - **Root Status**, ‘Live’ or ‘Dead’
 - **Size Category** (<0.5, 0.5-1, 1-2, 2-10)
3. Separate roots and soil organic matter (OM) from mineral soil by wet sieving. Before beginning the wet-sieving routine, determine whether the soil sample has been selected for Dilution Sampling (SOP D).
 - a. Massage the sample in the bucket with gentle manual pressure to break up large aggregates and OM pieces.
 - b. Thoroughly mix the slurry in the bucket by hand to separate small roots from mineral soil particles. At this point, roots and small pieces of (OM) should be floating on the surface.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- c. Remove large roots from the surface of the slurry.
 - i. Assemble the sieve stack; the 2 mm sieve should be on top of the 250 μm sieve, and the stack should be placed over one of the washing station grates.
 - ii. Using hands or forceps, pick large visible roots from the bucket and place in the 2 mm sieve (i.e., the top of the sieve stack).
 - iii. Wash mineral particles from the roots and be sure to rinse hands over the stack so as not to lose root particles.
 - iv. Transfer clean roots to a sorting container – i.e., a white enamel pan or equivalent with water. Sorting is carried out in a subsequent step.

- d. Once large roots have been picked from the surface of the slurry, pour PART of the slurry through the top of the sieve stack. This will begin to separate remaining roots and OM from mineral soil.
 - i. BE CAREFUL NOT TO OVERFLOW THE 250 μm SIEVE!
 - ii. Quickly remove large rocks from the surface of the 2 mm sieve as you go.
 - iii. When the 250 μm sieve is full, transfer the entire contents into a large plastic bin, tray, or equivalent. Set aside the sieve contents in the bin until the entire soil sample has been passed through the sieve stack.
 - iv. When checking the 250 μm sieve, transfer the roots from the 2 mm sieve into the sorting container from step (3.c.iv); transfer by turning the 2 mm sieve upside-down over the sorting container and using the washing station nozzle.
 - v. Continue pouring aliquots of the sample slurry from the bucket through the sieve stack, repeating (i)-(iii) immediately above, until the entire sample has passed through the stack.

- e. Place the clean 2 mm sieve back on top of the 250 μm sieve and decant the material that was set aside in the bin/tray in step (3.d.ii) back through the sieve stack. Mineral particles should be retained in the bin/tray.
 - i. To decant, let the mineral soil settle to the bottom then carefully but quickly pour off the water, roots and OM from the top and into the sieve stack.
 - ii. BE CAREFUL NOT TO OVERFLOW THE 250 μm SIEVE!
 - iii. Add more water to the bin/tray, and stir into a slurry to release more roots and OM from the mineral soil.
 - iv. Continue to rinse and pour through the sieve stack until only mineral soil is in the bin/tray. This may require between 2-10 rinses depending on soil type.

f. Transfer washed roots from both sieves to the sorting container.

4. Use forceps to pick all roots ≥ 1 cm length from the sorting container, and sort to **Size Category** and **Root Status** as you go.

- Use a wire gauge to determine the **Size Category**; the largest diameter of a root fragment should be used to classify the size.



- **VERY IMPORTANT:** To determine root diameter, you must pass the root through the gap *in the side* of the wire gauge; DO **NOT** insert the root through the larger hole.
- The wire gauge may be mounted on the side of the sieve using one of the larger gaps, enabling quick access for size classification.
- If only part of a root is alive, categorize the entire root as “live.” Dead roots are most often dark brown or black and brittle, while live roots are often lighter in color and flexible – i.e., they can typically be bent into a “U” shape without breaking.
- Make sure you use multiple attributes to classify roots.

5. Clip apart branched root systems into respective **Size Category** classes (see **Figure 8**):

- Clip only at branch points.
- **Size Category** is assessed at the largest end of the clipped segment.
- Do not clip at a given branch point if there are no ‘downstream’ changes in **Size Category**.
- Ignore branches that result in root fragments < 1 cm length.




Figure 8. Clipping a branched root system to Size Category. The orange bar indicates where two 1-2mm diameter roots are clipped from a ≥ 2 mm diameter root; the green bars indicate where 0.5-1mm diameter roots are clipped from larger roots; the blue bars indicate where roots < 0.5 mm diameter are clipped from larger roots. The orange circle is not clipped because there are no downstream changes in Size Category; the green circle is not clipped

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

because the fragment is < 1 cm length; the blue circle is not clipped because even though diameter within the circle is < 0.5mm, Size Category is assessed at the largest end, and clipping only occurs at branch points.

6. Place sorted roots into the pre-labeled envelopes created in step (2).
7. **If the sample has been randomly selected for dilution sampling**, set aside the residual fraction for processing via SOP D (i.e., root fragments < 1 cm mixed with organic material).
 - a. See SOP D, step (1) for guidance on randomly selecting cores for dilution sampling.
 - b. Create a record in the Belowground Biomass Lab Dilution app for the Dilution Sample that will be generated from the soil Sample ID.
 - c. Select required plot-level and soil sample information to identify the Dilution Sample.
 - i. **Optional barcode workflow:** scan the Sample ID barcode from the field to populate the record with required plot and sample data.
 - d. Save the Lab Dilution record.
8. Thoroughly clean the sieves and enamel pan with water between core/monolith samples.
9. Check sediment traps in the root washing station; if traps are full, dispose of sediment in an approved receptacle.
10. Gather roots from the same soil sample together to keep them organized. For example:
 - a. Place envelopes containing root samples into a paper bag to keep samples organized (lunch sack size works well); OR
 - b. If there are very few roots, coin envelopes may be paper clipped together.
 - c. **Optional Barcode Workflow:**
 - i. Keep the physical barcode originally associated with the field-collected soil sample – i.e., the Sample ID barcode on weatherproof paper – with the root subsamples as they are dried and weighed.
 - ii. The Sample ID barcode will aid in bringing up the correct record during Dry Mass data entry.

C.1.2 Dry Sieving Soils

1. Process soils using the different sized sieves as you would with the wet-sieving procedure, but do not apply water.
2. For each soil sample, label up to 8 coin envelopes with the information below. The total number needed depends on the number of **Root Status** x **Size Category** combinations in the sample. For large amounts of root biomass within a size class, use a clasp envelope instead.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Optional: Envelopes may be pre-labeled with a Type I barcode, in addition to human-readable information.

- **Collect Date**, date roots were sampled in the field; YYYYMMDD format
 - **Plot ID** and **Subplot ID**,
 - for 20m x 20m plots, subplotID = 31;
 - for 40m x 40m plots, subplotID = 21, 23, 39, or 41
 - **Clip Cell Number**, the 3 digits to the right of the last “_” in the clipID on the Clip List
 - **Core ID**, either ‘North’ or ‘South’
 - **Root Status**, ‘Live’ or ‘Dead’
 - **Size Category** (<0.5, 0.5-1, 1-2, 2-10)
3. Use a 2 mm sieve, a 250 µm sieve, and a pan bottom. Pass the sample through the sieve stack to separate roots from mineral soil and soil organic matter, and then transfer roots to a white enamel pan for picking.
 - a. The 2 mm sieve is useful for catching and removing large rocks from the sample, as well as larger roots
 - b. The 250 µm sieve is useful for capturing any roots that have passed through the 2 mm sieve. Roots ≥ 1 cm in length are not likely to pass through this finer mesh.
 - c. The white pan can be used to more easily differentiate small roots in the 250 µm soil fraction.
 4. From each sieve and the enamel pan, separate fine roots ≥ 1 cm in length from mineral soil and organic matter.
 - a. It is often helpful to pass no more than 10 – 20% of the sample through the sieve stack, as it makes it easier to spot roots.
 - b. Break up aggregates and organic matter pieces using gentle manual pressure.
 - c. Manually remove larger rocks from the top of the 2 mm sieve – but don’t spend more than several minutes.
 5. Use forceps to pick all roots ≥ 1 cm length from the enamel pan, sorting to **Size Category** and **Root Status** as you go; alternatively, you may sort to **Size Category** and **Root Status** after all roots ≥ 1 cm in length have been picked.
 - a. Use a wire gauge to determine the **Size Category**; the largest diameter of a root fragment should be used to classify the size.
 - b. **VERY IMPORTANT:** To determine root diameter, you must pass the root through the gap *in the side* of the wire gauge; DO NOT insert the root through the larger hole.
 - c. The wire gauge may be mounted on the side of the sieve using one of the larger gaps, enabling quick access for size classification.
 - d. If only part of a root is alive, categorize the entire root as “live.” Live roots are most readily distinguished from dead roots on the basis of color and friability; dead roots are



Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- often dark brown or black and brittle, while live roots are often lighter in color and flexible – i.e., they can typically be bent into a “U” shape without breaking.
- e. Place sorted roots into the pre-labeled envelopes created in step (2).
 - f. **If the sample has been randomly selected for dilution sampling**, set aside the residual fraction (i.e., root fragments < 1 cm mixed with organic material) for processing via SOP D.
 - g. Clean the 250 μm sieve and repeat all of step (**Error! Reference source not found.**) until the entire sample has been processed through the sieve stack.
6. Once all roots >1 cm in length have been picked and sorted, wash sediment from roots by using a clean 250 μm sieve. Sediment clinging to roots can significantly inflate weighed root biomass; thus the importance of gently washing dry roots once they are sieved.
 - a. Place a sorted group of roots into the 250 μm sieve and gently run water over the roots.
 - b. Use forceps to transfer the roots to a labeled coin envelope.
 - c. Repeat the above steps (a-b) for the remaining root samples.
 7. Thoroughly clean the sieves and enamel pan with water between soil samples.
 8. Gather sorted roots from the same soil sample together to keep them organized. For example:
 - a. Place envelopes containing root samples into a paper bag to keep samples organized (lunch sack size works well); OR
 - b. If there are very few roots, coin envelopes may be paper clipped together.
 - c. **Optional Barcode Workflow:**
 - i. Keep the physical barcode originally associated with the field-collected soil sample – i.e., the Sample ID barcode on weatherproof paper – with the root subsamples as they are dried and weighed.
 - ii. The Sample ID barcode will aid in bringing up the correct record during Dry Mass data entry.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

C.2 Drying, weighing, and processing belowground biomass samples

Washed roots should be placed in the drying oven as soon as possible following sieving.

1. Label groups of envelopes containing washed roots from the same soil sample with the date and time they are placed in the drying oven.
 - These data are the **Oven Start Date** and **Time** required during data entry.
 - **Critical step:** Labeling bags allows assessment of how long different batches of bags have been in the oven, especially when roots sampled on different days occupy the same oven.
2. Place labeled bags into a drying oven for a minimum of 48 h (longer is okay, but not required).
 - Dry all root diameters at 65 °C.
3. Remove bags of dried biomass from the drying oven, and label bags with **ovenOutDate/Time**.
 - Dried plant material should be weighed immediately after removing from the drying oven, as it will absorb moisture from the air if left in ambient room conditions (particularly in humid environments).
 - If using this method, it is helpful to remove bags from the oven and weigh one at a time.
 - Dried samples may also be stored for up to 30 days in ambient room conditions prior to weighing. Samples treated in this manner must be returned to the drying oven for 24 h prior to weighing, and must be weighed as above after removal from the oven.
 - If samples were initially dried and kept in storage, it is not necessary to record any additional drying times.
4. Organize all samples from the same **Plot ID**.
 - Weighing samples from the same **Plot ID** at the same time, and keeping samples grouped, will greatly facilitate subsequent grinding and pooling steps (SOP C.4).
5. Weigh each fine root sample using a mass balance (minimum 0.001 accuracy) and a weigh boat. Enter data in the Belowground Biomass Lab Weighing app (next step).

Optional workflow: Record data on the 'Lab Weighing' data sheet, then transcribe into the Lab Weighing app.

- a. For large volumes of biomass that do not readily fit into a large weighboat, use the following strategies:
 - i. Use a large plastic tray (or equivalent) instead of a weigh boat (see equipment list).
 - ii. Crush or chop the biomass to reduce volume so it will fit into a weigh boat.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- iii. Avoid splitting the biomass into subgroups for weighing, as uncertainty values must be added each time a subgroup is created.
 6. In the Lab Weighing app, create a record for each **Plot ID, Subplot ID** and **Date** combination (i.e., Clip Cell), and enter required parent-level data:
 - a. **Optional Barcode Workflow:** Scan the Sample ID barcode from the field to rapidly select the desired **Plot ID, Subplot ID** and **Date** for the record.
 - b. **Site ID;** the site from which root samples were collected (auto-populated if using barcodes).
 - c. **Plot ID;** from the list, select the plot, subplot and date associated with the root samples (auto-populated if using barcodes).
 - d. **Sample Mass Presence;** For each Soil Sampling Area (**North** and **South**), indicate which Size Category x Root Status combinations are present in the sample.
 - i. If no roots were found, select '**No (zero)**' mass for that category/status combination.
 - e. Create a child-level record for each dried root sample from a given Clip Cell, and enter:
 - i. **Oven Start Date/Time;** date (YYYYMMDD format) and time (24-h format) the sample was initially placed in the drying oven.
 - Enter only for initial drying event. Do not enter additional dates/times for samples stored at room temperature, and then re-dried prior to weighing.
 - ii. **Oven End Date/Time;** date and time the sample was initially removed from the drying oven.
 - iii. **Weigh Date;** date Dry Mass was weighed for the sample, YYYYMMDD format.
 - iv. **Dry Mass;** dried root sample mass, greatest precision possible (0.001 or 0.0001 g)
 - v. **Sub-Sample Fate;** defaults to 'active'. Select other value as appropriate.
 - vi. **Optional Barcode Workflow:** Link barcode(s) with a minimum of one root subsample for which Sample Mass Presence = 'Yes'.
 - vii. Save child-level record.
 - f. Repeat step (6.d) for all root samples from the same soil sample.
 - g. Save the parent-level record.
 7. Once all masses have been recorded for a given sampling bout:
 - a. Perform QA on a subset of samples (SOP C.3), or
 - b. Return dried fine roots to temporary storage at ambient conditions. Samples in temporary storage can then be weighed for QA as time permits.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

C.3 Data Quality Assurance

To quantify uncertainty associated with weighing dried biomass, a random selection of dried samples are re-weighed by a different technician than the person who originally weighed the biomass.

1. For each sampling event at a given site, randomly or haphazardly select 10% of dried, previously weighed samples for re-weighing.
 1. If QA weighing does not occur within 1 hour of the initial weighing, return the selected samples to the drying oven for 24 h prior to QA weighing. In humid environments, samples will pick up moisture from the atmosphere.
2. For root samples selected for QA, select the appropriate parent record in the Belowground Biomass Lab Weighing app, and edit to create a new child-level '**QA**' record.

If using the optional barcode workflow: Scan the field Sample ID barcode (**Figure 3**) from which the root subsample for which QA is desired. This will bring up the appropriate parent-level Lab Weighing record.

3. Enter required data into the new QA child-level record:
 - a. **QA Dry Mass**; select the 'Y' option from the drop-down.
 - b. **QA Sample List**; select the root subsample for which QA Dry Mass will be recorded from the list of previously weighed and entered root masses.
 - c. **Weigh Date**; date QA Dry Mass was weighed, YYYYMMDD format.
 - d. **Dry Mass**; dried QA root sample mass, greatest precision possible (0.001 or 0.0001 g)
 - e. Save the child-level QA record.
 - f. Save the parent record.
4. Return to step (2) above for additional QA samples.
5. After QA weighing, return plant material to temporary storage.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

C.4 Grinding and Pooling Biomass for Chemical Analysis and Archive

Overview

1. **Which samples are processed:** A subset of dried root samples are processed for chemical analysis and archive once QA masses have been recorded:
 - a. Samples with Root Status = 'live' must be processed for chemical analysis, and possibly archive (if there is sufficient sample).
 - b. Samples with Root Status = 'dead' are not processed further, and may be discarded once data have been successfully entered to the NEON database and have been checked for data entry errors.

2. **How samples are processed:** Pooled root samples are created and split for shipment to chemical analysis and archive facilities (see **Figure 3**).
 - a. To create a composite root sample, live roots within the same **Size Category** are pooled across the 'North' and 'South' cores that originate from the same **Clip Cell Number**.
 - b. The Belowground Biomass Grind and Pool app employs the logic in **Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.**Table 11** to determine which pooled samples should be created.
 - c. The pooled sample is created, ground and split into representative subsamples.
 - d. A maximum of 4 pooled root samples are created and ground per unique **Clip Cell Number** (one for each **Size Category**).

3. **Mandatory barcode workflow:** Sample containers shipped for external analysis or archive must have barcodes in addition to human-readable information on each container.
 - a. Barcodes are required by the [Stork Shipping Tool](#), and enable automatic creation of shipping manifests, as well as receipt and tracking forms for all relevant parties.
 - b. Apply barcodes to vials a minimum of 30 minutes before vials are used (**see SOP A**).
 - c. Barcodes on sample containers are linked to upstream root and soil collection information via the Belowground Biomass Grind and Pool app.

Procedural steps:

1. Use the Belowground Biomass Grind and Pool app to determine, based on the total mass of each **pooled** live root sample, which processing steps are required (see **Table 11**).
 - a. Create a parent-level record in the Grind and Pool app corresponding to each soil Sample ID collected in the field.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- b. Select the **Domain ID**, **Site ID** and **Sample ID List** using information written on the coin envelope, OR
 - i. **Optional Barcode Workflow:** Scan the barcode affixed to a dried root subsample envelope to bring up the Domain, Site, and list of samples available for pooling. If > 1 envelopes are barcoded, any envelope from the same soil sample may be scanned.
- c. Create and save a child-level record for each **Size Category**.
- d. The app displays the CN Sample ID and the BGC Archive ID fields, when sufficient sample is available according to the logic in **Table 11**.
- e. Save the parent record.

Table 11. Splitting and processing guidelines for fine root samples, based on pooled sample mass.

dryMass	Samples to create		Processing guidelines
	C:N sample	Archive sample	
<0.02 g	-	-	Do not process sample for C:N analysis or archive.
0.02 – 0.4 g	X		Do not grind; place entire pooled sample in scint vial. Use gloved hand to crush if necessary.
0.4 – 1 g	X		Grind entire sample to 40 mesh for C:N analysis
> 1 g	X	X	Grind entire sample to 20 mesh; use splitter to generate a 0.4 g subsample that is ground to 40 mesh for C:N analysis; archive remainder of 20 mesh grind.

2. Once records have been created for all samples:
 - a. Filter and download the data for the records that match the samples, and
 - b. Use a return-address template to print **CN Sample ID** and **BGC Archive ID** labels for those pooled root samples that have sufficient mass to warrant processing.
 - c. Label vials for shipment to external analysis, and possibly, archive. Orient labels vertically so the label does not overlap the mandatory barcode.
 - d. **Optional Barcode Workflow:** Retain a barcode affixed to an envelope for each group of root samples from the same soil sample, and keep with the associated vials. The barcode will be subsequently used to more rapidly link vial barcodes with the correct Grinding and Pooling records.
3. Grind and split oven-dried pooled root samples according to the logic in **Table 11**, and place splits into the appropriately labeled 20 mL vials.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- a. Use an appropriately sized splitter or microsampler to generate representative sample splits. *DO NOT create splits with a scoopula or a spatula; these tools should only be used to transfer an ENTIRE split into a vial.*
 - b. Create a full vial for archive if possible. If a split is too large to fit into a vial in its entirety, continue splitting until the desired volume is obtained.
 - c. Clean grinding tools thoroughly between samples:
 - i. For a grinding mill, clean with compressed air.
 - ii. Clean mortar and pestle with a kimwipe and ethanol.
 - d. Once pooled samples have been ground and sealed into vials, excess ground biomass may be discarded.
4. **Mandatory Barcode Workflow:** Link vial barcodes with Grinding and Pooling records previously created in step (1).
- a. Filter and find the desired parent record for a given group of vials from the same soil sample.
 - i. **Optional Barcode Workflow:** Scan the root envelope barcode associated with a group of vials to bring up the desired parent record.
 - b. Open and edit each child-level record, and scan in the required **CN Sample Barcode**, and if sufficient sample was present, the required **BGC Archive Barcode**.
 - c. Save each child record.
 - d. Save the parent record.
5. See **SOP F** for shipping instructions.

C.5 Equipment maintenance

- Balances should be calibrated with a standard calibration weight set:
 - After initial installation.
 - Any time the balance is moved to a new surface.
 - Every 6 months.
 - If you suspect readings are inaccurate for any reason.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

SOP D Dilution Sampling for Fine Root Fragments

Goals

- Quantify the ratio of root fragments < 1 cm length to organic material in the residual fraction for selected soil samples.
- Collect required dilution sampling data:
 - The preferred method for data collection is the Belowground Biomass Lab Dilution application.
 - The Belowground Biomass Sampling Fulcrum Manual on the SSL contains detailed data entry instructions.

Overview

1. **When samples are processed:** Dilution sampling for quantifying fine root fragments < 1 cm length begins after a soil sample has been sieved and all roots \geq 1 cm length have been picked from the residual fraction (see SOP C.1).
 - It is acceptable to pause overnight between execution of SOP C and SOP D.
 - Store labeled residual fractions overnight at 4 °C in a sealed container (e.g., labeled 50 mL tube).
2. **Which samples are processed:** Fine root fragments are quantified each time the fine root biomass protocol is implemented by dilution sampling. Twenty (20) soil samples are selected for dilution sampling in a spatially balanced manner. The goal is to select soil samples such that as much of the tower airshed area as possible is represented by the final dilution sample set.

To determine which samples are selected:

- a. Were greater than 20 soil samples collected in total from all plots?
 - i. If **YES**, proceed to (b).
 - ii. If **NO**, generate a dilution sample from each soil sample.
- b. Was a soil sample collected from each plot?
 - i. If **YES** and there are thirty 20m x 20m short-stature vegetation plots (**Figure 1, left**): Randomly select 1 sample per plot from the plots with the 20 lowest Morton Order numbers.
 - ii. If **YES** and there are twenty 40m x 40m tall-stature vegetation plots (**Figure 1, right**): Randomly select 1 sample per plot.
 - iii. If **NO**, soil samples were not collected from each plot:
 1. Proceed to (c) for 20m x 20m short-stature plots
 2. Proceed to (d) for 40m x 40m tall-stature plots.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- c. Was a soil sample collected from 20 plots or more?
- i. If **YES**: For those plots with **Root Sampling Possible** = 'Yes', randomly select 1 sample per plot from the plots with the 20 lowest Morton Order numbers.
 - ii. If **NO**, soil samples were collected from < 20 plots:
 1. For those plots with **Root Sampling Possible** = 'Yes', randomly select 1 sample per plot.
 2. Select additional samples from the remaining pool according to Morton Order (lowest to highest) until a total sample size of 20 is reached.
- d. For those 40m x 40m plots with **Root Sampling Possible** = 'Yes', was a soil sample collected from both 20m x 20m subplots in each plot?
- i. If **YES**, samples were collected from both 20m x 20m subplots per plot:
 1. Randomly select one 20m x 20m subplot per plot. If both North and South samples were collected from the chosen subplot, randomly select 1 soil sample (North or South). Total dilution sample size is < 20 at this point.
 2. Select additional dilution samples by plot according to Morton Order (lowest to highest). This time, select a soil sample from the 20m x 20m subplot that was NOT randomly selected in (1) immediately above. If both North and South samples were collected from the chosen subplot, randomly select 1 soil sample (North or South).
 3. Continue down the Morton Order list until 20 dilution samples have been selected.
 - ii. If **NO**, samples were not collected from both 20m x 20m subplots in each plot: proceed to (e).
- e. For those 40m x 40m plots with **Root Sampling Possible** = 'Yes', and for at least one plot a soil sample was collected from only one 20m x 20m subplot:
- i. For all plots in which only one subplot generated a sample: If both North and South soil samples were collected, randomly select 1 soil sample per plot for dilution sampling.
 - ii. For all plots in which two subplots generated a sample:
 1. Randomly select one 20m x 20m subplot per plot. If both North and South samples were collected from the chosen subplot, randomly

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

select 1 soil sample (North or South). Total dilution sample size is < 20 at this point.

2. Randomly select additional dilution samples from 20m x 20m subplots that were NOT initially chosen in (1) immediately above. If both North and South samples were collected, randomly select 1 soil sample (North or South).

- iii. If a dilution sample size of 20 still is not met, randomly select additional samples from the remaining pool until 20 total samples are selected.

3. How samples are processed:

- a. The entire residual fraction is suspended in water and vortexed to homogenize, creating a **Dilution Sample**.
- b. **Dilution Subsamples** (n=10) are extracted from the vortexing **Dilution Sample**.
- c. **Dilution Subsamples** are sorted to root and soil organic matter components, and then dried and weighed to enable calculation of total root fragment mass in the residual fraction.



- i. ***Masses must be recorded to minimum 0.001 g accuracy; 0.0001 g accuracy is preferred.***

- d. Multiple variables are optimized on a per soil type basis to generate root fragment and soil organic material masses that are sufficiently large such that reliable masses can be weighed, but that are not so large that sorting requires more than an average of 15 min per Dilution Subsample.

4. Digital workflow:

- a. Records in the Belowground Biomass Lab Dilution app are created for dilution samples in SOP C.1.
- b. **Pre-oven dry**: Previously created records are edited to create child-level records containing Dilution Subsample IDs. The Tin ID is added for each child record and the record is saved.
- c. **Post-oven dry**: Each child record is edited to add **Dry Mass** and the record is saved.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Dilution Sampling Steps

For selected residual fraction samples, the steps below describe how to separate root fragments from soil organic matter and quantify root fragment biomass with a relatively time-efficient technique.

1. Take the residual fraction still in the 250 µm sieve from SOP C, and carefully wash with the root washer nozzle. The residual fraction should be free from mineral soil particles at this point.
2. Transfer the consolidated residual fraction to a beaker – i.e. all roots < 1 cm length from a given soil sample – and suspend the sample in water. **Use distilled water** from this point forward, including water used to rinse the sieve that is then collected; mineral build-up on weighing tins has been shown to significantly alter perceived root and organic matter masses.
 - a. Based on the size of the residual fraction, choose either a 1 L, 2 L, or 4 L beaker. Note that the size of the beaker can be varied from core to core, depending on the size of the residual fraction.



TIP: The goal is to sufficiently dilute the residual fraction so that not too many roots need to be picked and sorted, but not dilute so much that there are too few roots to weigh accurately once they are dry. If in doubt, use the 1 L beaker, and dilute further if necessary.

- b. Manually transfer as much of the residual fraction as possible to the beaker. Use a scoopula, spatula or equivalent.
- c. Transfer any remaining residual fraction from the 250 µm sieve to the beaker; use a squirt bottle and ≤ 500 mL of water to rinse the sieve.
- d. Carefully fill the beaker with distilled water to approximately ¾ full (e.g., 750 mL, 1.5 L, or 3 L). It is helpful to fill to one of the pre-marked graduations on the beaker, as an accurate volume at this step will be used to estimate the total mass of root fragments < 1 cm length.

In the steps that follow, when data entry is required, data may be entered directly into the digital workflow by editing an existing record, or may be recorded on paper for multiple samples, then transcribed.

3. Record required **Dilution Sample** metadata.
 - **Sample Volume;** volume of water used to suspend residual fraction in beaker; best precision possible, e.g., nearest 10 mL
 - **Processed Date;** date dilution sampling is carried out, YYYYMMDD format
4. **Dilution Sample Fate;** set to 'lost' if equipment breakage occurs during subsequent steps and sample is compromised. Label 10 pairs (n=20 total) of aluminum weighing tins to hold the 10 Dilution Subsamples.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- Tins should be pre-numbered with a unique **Tin ID** (e.g. 1, 2, 3,..., 20, etc.)(see **Figure 9**). The **Tin ID** is tracked with the sample, rather than labeling each tin with sample information.
 - For each pair of tins, one is for root fragments, and the other is for organic material.
5. Pre-weigh each empty, dry tin with a microbalance; nearest 0.001 g (minimum), or nearest 0.0001 g (preferred).
 - a. Tins should be oven-dried at 65 °C for 15-30 min prior to weighing to remove adsorbed moisture (use whichever temperature is most convenient based on existing oven temperatures). The microbalance will detect moisture adsorbed from the air in humid environments.
 - b. Oven-dried tins may be stored in a desiccator between drying and weighing.
 - c. Associate tin data with previously created Lab Dilution records:
 - **Tin ID**; the unique number assigned to the tin.
 - **Empty Tin Mass**; the mass of the clean, dry, empty tin.
 - (Paper workflow) **Dilution Subsample Number**; 1-10, technician assigned, needed to track pairs of tins from the same Dilution Subsample (**Figure 9**).
 6. Work in pairs to generate 10 **Dilution Subsamples** from the aqueous suspended **Dilution Sample** in the beaker. Consult the training video for a visual demonstration of the following steps:
 - a. [Person1] Turn the plate mixer on high, and vortex the aqueous suspended Dilution Sample thoroughly (approx. 10 s from the start of vortexing).
 - b. [Person1] Turn off the mixer, and quickly plunge the suspension to stop the vortex and randomize the sample in the water.
 - c. [Person2] Take a 20 mL Dilution Subsample from the middle of the water volume in the beaker using the customized syringe, and transfer to one of the ‘OM’ tins.

NOTE: In addition to adjusting the beaker **Sample Volume** in step (3) above, the Dilution Subsample **Aliquot Volume** obtained with the syringe can also be adjusted from 20 mL to optimize the amount of material needed for sorting and weighing. For example, collect 10 mL if the suspension is particularly dense.
 - d. [Person2] Back off the plunger in the syringe to the 5 mL mark. Rinse the interior of the syringe with the squirt bottle, and transfer the rinse to the same tin.
 7. Record required Dilution Subsampling metadata:
 - **Aliquot Volume**; the volume of the subsample taken with the syringe; nearest 1 mL.
 - The volume of water from the squirt bottle should not be added to this number.
 - (Paper workflow) **Subsample Type**; the type of material the tin will hold after picking and sorting is complete; the tin initially receiving the mixed sub-sample should be

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Subsample Type = 'OM', and the tin into which roots are sorted should be **Subsample Type = 'ROOT.'** Repeat steps (5) and (6) until 10 sub-samples have been transferred to 10 'OM' tins (**Figure 9**).

8. For each of the 10 Dilution Subsamples, carefully pick and sort root fragments from organic material and transfer the roots to the 'ROOT' tin of the pair (**Figure 9**).
 - A small amount of water in the 'ROOT' tin aids in transferring root material.
 - **Aim for 10-15 min sorting time per tin pair**; adjust the **Sample Volume** in the beaker and the **Aliquot Volume** in the syringe as necessary.




Figure 9. Ten pairs of labeled aluminum weighing tins for separating roots from OM. Dilution Subsamples are initially transferred to the OM tins via syringe, and roots are then sorted into the ROOT tins. Each tin has a unique Tin ID.

9. Carefully transfer tins to a 65 °C drying oven for 48 h. Record:
 - **Oven Start Date/Time**; the date and time the samples were placed in the drying oven.

Tips:

- Use a tray to move batches of tins in the laboratory.
- Heavy duty metal trays may be placed directly in the drying oven with all of the samples.
- Do not leave samples on light-weight trays in the drying oven. Light-weight metal trays occasionally twist when heated which will cause samples to spill.
- Place a large piece of cardboard over tins to prevent oven fans from blowing very light dried samples out of the tins.

10. Repeat steps (2) – (9) for additional soil samples.

11. Once tins are dry, weigh the total mass of each 'tin+ROOT' or 'tin+OM' with a microbalance.

Record required 'Lab Dilution' data:

- **Oven End Date/Time**; the date and time samples were removed from the drying oven.
- **Dry Mass**; the mass of the dry 'tin+ROOT' or 'tin+OM' material; nearest 0.001 g (minimum), nearest 0.0001 g (preferred).

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

SOP E Data Entry and Verification

Mobile applications are the preferred mechanism for data entry. Data should be entered into the protocol-specific application as they are being collected, whenever possible, to minimize data transcription and improve data quality. For detailed instructions on protocol-specific data entry into mobile devices, see the internal NEON Sampling Support Library ([SSL](#)). Mobile devices should be synced at the end of each field day, where possible; alternatively, devices should be synced immediately upon return to the Domain Support Facility.

However, given the potential for mobile devices to fail under field conditions, it is imperative that paper datasheets are always available to record data. Paper datasheets should be carried along with the mobile devices to sampling locations at all times. As a best practice, field data collected on paper datasheets should be digitally transcribed within 7 days of collection or the end of a sampling bout (where applicable). However, given logistical constraints, the maximum timeline for entering data is within 14 days of collection or the end of a sampling bout (where applicable). See RD[04] for complete instructions regarding manual data transcription.

E.1 Digital Data Workflow

Data collected in the field:

1. The **Clip ID**, **Collect Date** and sampling area (North/South) are used to construct the soil **Sample ID**. Make sure these data are entered correctly before finalizing Field records.
2. Finalizing Field records and syncing will make **Sample IDs** available for further data entry in the Lab Weighing, Lab Dilution, and Grinding and Pooling applications.
 - a. If corrections to either the Clip ID, Collect Date, or sampling area are required after a Sample ID has been selected in a downstream application:
 - i. Make correction(s) in the Belowground Biomass Field app and save.
 - ii. Open, edit, and save each downstream parent and child record in order to propagate the update.
 - b. Consult the plant Belowground Biomass Sampling Fulcrum User Manual on the SSL for more detail.

Lab Weighing and Grinding and Pooling:

1. The **Sample ID**, **Size Category** and **Root Status** information are used to construct the **Subsample ID** that is associated with a given Dry Mass value.
2. The downstream Grinding and Pooling application uses masses from available Subsample IDs to determine which subsamples are pooled, processed and shipped to external facilities.
 - a. If corrections to data used to construct Subsample IDs are required:
 - i. Make correction(s) in the Belowground Biomass Lab Weighing app and save.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- ii. Open, edit, and save each downstream parent and child record in order to propagate the update.

Lab Dilution data:

1. The **Sample ID** from the Field application is used to construct the **Dilution Sample ID**.
2. If corrections to either the Clip ID, Collect Date, or sampling area are required in the Field app after a Sample ID has been selected in the Lab Dilution app:
 - a. Make correction(s) in the Belowground Biomass Field app and save.
 - b. Open, edit, and save each Lab Dilution parent and child record in order to propagate the update.

See the Data Management Protocol (RD[04]) for detailed, protocol-specific Data Management SOPs. See training materials on the SSL for detailed data ingest guidance via the NEON digital workflow.

E.2 Field Datasheets

1. Transcribe data from the plant Belowground Biomass Field Datasheets (RD[05]) to the Field application.
 - Consult the Belowground Biomass Fulcrum Manual on the SSL to determine appropriate values and formats for each field in the ingest table.
2. If a representative clip cell did not support belowground biomass soil sampling, noted as ‘Root Sampling Possible = N’ in the **remarks** field of the Field Datasheet, enter in the Field ingest:
 - **Root Sampling Possible = ‘No’**
3. Update permanent digital versions of the Clip Lists with **date** and **status = ‘5’** data recorded in the field.

E.3 Lab Datasheets

- Transcribe data from the ‘Lab Weighing’ datasheet into the ‘Lab Weighing’ application.
 - If a core sample contained no fine root biomass within a given **Size Category**, select ‘No’ in the appropriate sample Presence/Absence field.
- Transcribe data from the ‘Lab Dilution’ datasheet into the ‘Lab Dilution’ application.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

SOP F Sample Shipment

Information included in this SOP conveys science-based packaging, shipping, and handling requirements for these samples, not lab-specific or logistical demands. For lab-specific shipping information, reference the “Shipping Information for External Facilities” document on [CLA’s NEON intranet site](#).

- **Timelines:** Dried, root samples may be stored indefinitely before shipping.
- **Storage/Shipping Conditions:** Dried root samples sealed in 20 mL plastic or glass vials may be shipped at ambient temperature without preservatives.
- **Grouping/Splitting Samples:** Samples originating from the same clip cell should be grouped together for shipment, if possible.

F.1 Shipment Preparation Procedure

1. Take scintillation vial box containing processed samples out of temporary storage for shipment.
2. Wrap the box in bubble wrap and tape securely, then place in a FedEx box for shipment.
3. Navigate to the “Shipping Information for External Facilities” document on CLA’s NEON intranet site.
 - Determine which additional documentation is required to accompany the shipment (e.g., USDA permits and/or cover letters).
 - Check the intranet instructions frequently, *as shipping instructions are subject to change*.
4. Print out required documents (if needed), and include in the shipment box.
5. Prepare a shipping inventory detailing the contents of the shipment, using the appropriate shipping applications. These include:
 - Shipping: Shipment Creation
 - Shipping: Shipment Review
 - [Stork Shipment Verification Tool](#)
6. Include a printed copy of the inventory in the shipment box.
7. Address shipping label appropriately, and ship ground.
8. Send an electronic copy of the shipping inventory to the email addresses listed in the “Shipping Information for External Facilities” document. Include the shipment Tracking Number in the email.

F.2 Laboratory Contact Information and Shipping / Receipt Days

See the “Shipping Information for External Facilities” and “External Facilities Closure Dates” documents on [CLA’s NEON intranet site](#).

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

8 REFERENCES

- Berhongaray, G., J. S. King, I. A. Janssens, and R. Ceulemans. 2013. An optimized fine root sampling methodology balancing accuracy and time investment. *Plant and Soil* 366:351-361.
- Burton, A. J., and K. S. Pregitzer. 2008. Measuring forest floor, mineral soil, and root carbon stocks. Pages 129-142 *in* C. M. Hoover, editor. *Field measurements for forest carbon monitoring*. Springer-Verlag, New York.
- Koteen, L., and D. Baldocchi. 2013. A randomization method for efficiently and accurately processing fine roots, and separating them from debris, in the laboratory. *Plant and Soil* 363:383-398.
- Milchunas, D. G., and W. K. Lauenroth. 2001. Belowground primary production by carbon isotope decay and longterm root biomass dynamics. *Ecosystems* 4:139-150.
- Steinaker, D. F., and S. D. Wilson. 2005. Belowground litter contributions to nitrogen cycling at a northern grassland-forest boundary. *Ecology* 86:2825-2833.
- Taylor, B. N., K. V. Beidler, E. R. Cooper, A. E. Strand, and S. G. Pritchard. 2013. Sampling volume in root studies: the pitfalls of under-sampling exposed using accumulation curves. *Ecology Letters* 16:862-869.
- Tierney, G. L., and T. J. Fahey. 2007. Estimating belowground primary productivity. Pages 120-141 *in* T. J. Fahey and A. K. Knapp, editors. *Principles and standards for measuring primary production*. Oxford University Press, New York.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

APPENDIX A DATASHEETS

The following datasheets are associated with this protocol:

Table 12. Datasheets associated with this protocol

NEON Doc. #	Title
NEON.DOC.002135	Datasheets for TOS Protocol and Procedure: Plant Belowground Biomass Sampling

These datasheets can be found in Agile or the NEON Document Warehouse.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

APPENDIX B QUICK REFERENCES

B.1 Soil Core Sampling in the Field

1. Select the first available clip cell from the Clip List, and assess for suitability. Be sure to check if Herbaceous Biomass sampling has already occurred in the current season, and if a cell has already been clipped, choose the clipped cell to co-locate sampling.
2. Take one core from the North sampling area, and another core from the South sampling area.
3. Measure and record the depth of the core hole.
4. Create a label for each core on waterproof paper, and be sure to record all required sampling metadata.
5. Record the date and time the core was placed in the cooler in the field.

QUALITY DEPENDS ON PROPER:

- Labeling of core samples.
- Measurement of core hole depth.
- Maintaining samples in cold storage.

B.2 Processing Belowground Biomass Samples in the Laboratory

1. Figure out ahead of time which 20 cores will be randomly selected for Dilution Sampling.
2. Soak cores prior to sieving in a plastic bin or bucket.
3. Process one small aliquot of the core through the sieve stack at a time – ***avoid overflowing the fine bottom sieve!***
4. Use a wire gauge to determine root **sizeCategory** – ***always measure root diameter through the gap in side of the wire gauge.*** Do NOT pass the root through the hole of the gauge.
5. Sort roots by **sizeCategory** and **rootStatus**.
6. Dry sorted roots for a minimum of 48 h at 65 °C.

QUALITY DEPENDS ON PROPER:

- Passing the samples through the sieves – **DO NOT OVERFLOW!**
- Removal of mineral soil and organic material from roots.
- Use of the wire gauge for **sizeCategory** sorting.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

B.3 Dilution Sampling for Fine Root Fragments

1. Retain the residual fraction from randomly selected cores for Dilution Sampling.
2. Label all sample tins to ensure that samples can be tracked.
3. Work in pairs to quickly obtain representative subsamples of the suspended residual fraction.
4. Adjust the size of the beaker (**sampleVolume**) and the size of the sub-sample (**subSampleVolume**) to keep sorting time manageable.
 - a. Aim for approximately 10-15 minutes per tin pair.
5. Dry sorted root fragments and OM for a minimum of 48 h at 65 °C.

QUALITY DEPENDS ON:

- Choosing an appropriately sized beaker for suspending the residual fraction. Too concentrated will take too long to sort, and too dilute will result in masses too light to accurately weigh.
- Dispersing the residual fraction evenly throughout the sample volume in the beaker to generate representative subsamples.
- Accurately distinguishing roots from organic material.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

APPENDIX C REMINDERS

TBD

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

APPENDIX D ESTIMATED DATES FOR ONSET AND CESSATION OF SAMPLING

Soil sampling for plant Belowground Biomass is ideally timed to broadly coincide with the peak aboveground biomass clip harvest, due to the scientific utility of relatively coincident estimates of both aboveground and belowground biomass. As such, dates listed in **Table 13** below are the estimated dates after which greenness begins to decrease at each site, and in theory, after which the majority of above and belowground biomass has been produced. Dates are averages of 2001-2009 MODIS-EVI satellite phenology data. However, soil moisture also influences the timing of sampling, and as such, dates below may need to be adjusted at a given site based on soil moisture conditions within a given year. Soil core sampling should be concluded within 6 weeks of the actual start date.

Table 13. Estimated average dates after which greenness begins to decrease for each NEON site based on MODIS-EVI phenology data. Ideally, soil core sampling and aboveground biomass clip harvests should occur on or near these dates.

Domain	Site	Start Date (MM/DD)	Additional Information
01	BART	07/17	Date is earlier than indicated by MODIS due to understory consistently senescing before overstory.
	HARV	07/17	Date is earlier than indicated by MODIS due to understory consistently senescing before overstory.
02	BLAN	07/29	
	SCBI	08/08	
	SERC	08/08	
03	DSNY	07/09	
	JERC	08/08	
	OSBS	07/09	
04	GUAN	10/15	
	LAJA	10/01	
05	STEI	08/03	
	TREE	08/03	
	UNDE	08/03	
06	KONA	07/28	
	KONZ	07/29	
	UKFS	07/15	
07	GRSM	08/03	
	MLBS	08/08	
	ORNL	07/29	
08	DELA	07/24	
	LENO	07/19	
	TALL	07/14	
09	DCFS	07/24	

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

Domain	Site	Start Date (MM/DD)	Additional Information
	NOGP	07/19	
	WOOD	07/29	
10	CPER	07/29	Soil may be too hard for coring at greenness decrease date; earlier start date timed to soil moisture may be advised (late spring).
	RMNP	07/29	
	STER	2-4 wks before crop harvest	If plot is fallow with no cover crop, sample at peak green of surrounding vegetation.
11	CLBJ	10/01	
	OAES	10/16	
12	YELL	07/09	
13	MOAB	08/12	
	NIWO	08/08	
14	JORN	09/02	
	SRER	08/28	
15	ONAQ	06/18	
16	ABBY	07/23	
	WREF	07/29	
17	SJER	04/05	
	SOAP	07/04	
	TEAK	07/24	
18	BARR	07/29	
	TOOL	07/24	
19	BONA	07/24	
	DEJU	07/29	
	HEAL	07/29	
20	PUUM	TBD	

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

APPENDIX E SITE-SPECIFIC MODIFICATIONS

Table 14. Summary of site-specific belowground biomass sampling modifications and supporting rationale.

Domain	Site(s)	Modification Type	Modification	Standard Rule	Rationale for Change
D18/19	BARR TOOL BONA DEJU HEAL	Clarification: Definition of soil surface	Site-specific criteria to determine where the soil surface begins.	Soil surface and litter layer are differentiated by former lacking discernable plant parts.	Fibric plant structures persist into soil organic layer; roots grow into living moss layers.

E.1 D18/19 Site-specific Modifications

1. To determine where the soil surface begins, use the presence of roots, color and texture:
 - a. The presence of roots determines the position of the soil surface. This means we will begin collecting a soil sample at depths where the substrate may still be comprised of identifiable plant parts (live or dead).
 - b. When vascular plant roots are absent, identify the boundary between mostly live or mostly dead plant material, and call this boundary the top of the organic soil horizon.
 - i. Dead plant material may still appear fibric and very much like a discernable plant part at this boundary.
 - ii. Finding the boundary can be difficult because live plant material, roots, and dead plant material will often transition along a continuum from the surface downward.
 - iii. To sample consistently, use color (green to brown), texture (soft and friable material should be mostly dead), and presence of roots.
2. To collect a soil sample:
 - a. Use clippers or equivalent to remove surface vegetation and reveal the soil surface.
 - i. Remove vegetation from a surface area of approximately 10 cm x 10 cm until roots are apparent or until the surface of the organic soil layer is apparent (using criteria above).
 - b. Collect a soil sample to 30 cm maximum depth or refusal, whichever comes first.
 - c. Remove the soil sample and process according to SOP B.

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

3. To process soil samples with a fibric surface soil:
 - a. Cut and separate fibric organic material from more mineral-rich and decomposed organic soil before sieving – fibric material will not sieve easily and should not be passed through the sieve stack. Typical organic soil will pass through the sieve stack.
 - b. From the fibric fraction, manually pluck larger roots and then float and wet-pick the remaining material to remove smaller diameter roots and fragments ≥ 1 cm length.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

APPENDIX F SOIL CORE ASSEMBLY




Figure 10. Component parts of the Giddings soil core assembly.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

APPENDIX G MANAGING EXPOSURE TO TOXICODENDRON SPECIES

General guidelines for preventing and mitigating exposure to toxic oils from *Toxicodendron* species can be found in RD[12].

The following are protocol-specific best-practice techniques for minimizing exposure to toxic oil during plant Belowground Biomass Sampling.

Table 15. Equipment list – Minimizing exposure to toxic oils from roots of *Toxicodendron spp.* that may be encountered during plant Belowground Biomass Sampling.

Item No.	R/S	Description	Purpose	Quantity
Durable Items				
	R	Labeled clippers, dedicated to clipping <i>Toxicodendron spp.</i> (see Table 5)	Prevent spread of toxic oils to multiple clippers	1
	R	Labeled sieve set(s), dedicated to sieving samples containing <i>Toxicodendron</i> . (Set contains 2mm sieve and 250 µm sieve. See Table 5 .)	Prevent spread of toxic oils to multiple sieves.	As needed
	R	Labeled forceps, blunt tip, stainless steel; dedicated to <i>Toxicodendron</i> samples	Prevent spread of toxic oils to multiple forceps.	As needed
Consumable Items				
	R	See RD[12]		

1. Prior to field work:

- a. Count out coin envelopes or clasp envelopes for storing and drying root samples that will likely contain *Toxicodendron* biomass. Don't mix samples containing *Toxicodendron* biomass with any other samples.
- b. Pre-weigh (to nearest 0.01 g) and label each envelope that will be used for storing and drying soil samples containing *Toxicodendron* biomass. Once the weight of each empty envelope is written on the envelope, the biomass inside the bag will never have to be touched after it is initially placed in the bag.

2. To collect soil samples containing *Toxicodendron* biomass in the field:

- Before collecting the soil sample, use a pair of clippers dedicated solely to clipping *Toxicodendron spp* to clip and remove any aboveground *Toxicodendron* biomass that would be contacted while sampling.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

- Bring a clean, new plastic bag to the field for storing and transporting contaminated gloves, soil sampling equipment, and clippers after use.
3. **To process *Toxicodendron* biomass in the laboratory:**
 - a. Use sieves and forceps dedicated to processing root samples containing *Toxicodendron* biomass. Wash sieves and forceps with Tecnu (or equivalent) following each use.
 - b. Minimize potential spread of toxic oil by putting envelopes containing *Toxicodendron* roots into the same drying oven every time.
 - c. When drying is complete, clean drying oven shelves used for drying *Toxicodendron* biomass with hot water and Tecnu. Wear appropriate PPE when cleaning.
 - d. Record weight of bag + dried biomass to nearest 0.01 g, and also record weight of individual empty bag (to 0.01 g) on data sheets. Dried *Toxicodendron* biomass should never leave the bag.
 4. After weighing, dispose of root samples containing *Toxicodendron* biomass. At this point in time, *Toxicodendron* tissue will not be ground for chemical analysis or archived.

APPENDIX H CLIPCELLNUMBER COORDINATES AND MAPS

Plant Belowground Biomass Sampling and peak biomass clip harvest sampling ideally take place in the same clip cell in a given Tower plot. NEON Field Operations technicians must track the clip cell associated with soil sampling and peak biomass clipping on the Clip Lists provided by Science Operations. When the Herbaceous Biomass clip harvest (RD[11]) precedes soil sampling in the field, it is necessary to physically locate the clip cell in which the peak biomass clip occurred.

H.1 Maps of clipCellNumber by subplotID




Figure 11. Map of clipCellNumbers in a 20m x 20m base plot (subplotID = 31 in provided Clip Lists). Red squares indicate nested subplots used for diversity sampling; clip cells that significantly overlap red squares are not used for fine root soil coring or clip sampling. However, cells with minimal overlap (e.g., 48-54, 68-72, 145-149) do support these sampling activities.




Figure 12. Map of clipCellNumbers for **subplotID = 21** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling.




Figure 13. Map of clipCellNumbers for **subplotID = 23** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling.




Figure 14. Map of clipCellNumbers for **subplotID = 39** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling.




Figure 15. Map of clipCellNumbers for **subplotID = 41** in a 40m x 40m Tower base plot. Cells that overlap nested subplots indicated by red squares are not used for fine root soil core or clip sampling.

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

H.2 Coordinates for clipCellNumbers by subplotID

Table 16. List of clipCellNumbers by subplotID and associated easting and northing coordinates. Coordinates correspond to the SW corner of a 0.1m x 2m Clip Strip, and indicate the distance in meters relative to the SW corner of the plot (subplotID = 31) or subplot (subplotID = 21, 23, 39, 41).

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
1	1	251	501	751	1.2	1.5
2	2	252	502	752	1.7	1.5
3	3	253	503	753	2.2	1.5
4	4	254	504	754	2.7	1.5
5	5	255	505	755	3.2	1.5
6	6	256	506	756	3.7	1.5
7	7	257	507	757	4.2	1.5
8	8	258	508	758	4.7	1.5
9	9	259	509	759	5.2	1.5
10	10	260	510	760	5.7	1.5
11	11	261	511	761	6.2	1.5
12	12	262	512	762	6.7	1.5
13	13	263	513	763	7.2	1.5
14	14	264	514	764	7.7	1.5
15	15	265	515	765	8.2	1.5
16	16	266	516	766	8.7	1.5
17	17	267	517	767	9.2	1.5
18	18	268	518	768	9.7	1.5
19	19	269	519	769	10.2	1.5
20	20	270	520	770	10.7	1.5
21	21	271	521	771	11.2	1.5
22	22	272	522	772	11.7	1.5
23	23	273	523	773	12.2	1.5
24	24	274	524	774	12.7	1.5
25	25	275	525	775	13.2	1.5
26	26	276	526	776	13.7	1.5
27	27	277	527	777	14.2	1.5
28	28	278	528	778	14.7	1.5
29	29	279	529	779	15.2	1.5
30	30	280	530	780	15.7	1.5
31	31	281	531	781	16.2	1.5
32	32	282	532	782	16.7	1.5
33	33	283	533	783	17.2	1.5
34	34	284	534	784	17.7	1.5
35	35	285	535	785	18.2	1.5
36	36	286	536	786	18.7	1.5
37	37	287	537	787	1.2	4.5

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
38	38	288	538	788	1.7	4.5
39	39	289	539	789	2.2	4.5
40	40	290	540	790	2.7	4.5
41	41	291	541	791	3.2	4.5
42	42	292	542	792	3.7	4.5
43	43	293	543	793	4.2	4.5
44	44	294	544	794	4.7	4.5
45	45	295	545	795	5.2	4.5
46	46	296	546	796	5.7	4.5
47	47	297	547	797	6.2	4.5
48	48	298	548	798	6.7	4.5
49	49	299	549	799	7.2	4.5
50	50	300	550	800	7.7	4.5
51	51	301	551	801	8.2	4.5
52	52	302	552	802	8.7	4.5
53	53	303	553	803	9.2	4.5
54	54	304	554	804	9.7	4.5
55	55	305	555	805	10.2	4.5
56	56	306	556	806	10.7	4.5
57	57	307	557	807	11.2	4.5
58	58	308	558	808	11.7	4.5
59	59	309	559	809	12.2	4.5
60	60	310	560	810	12.7	4.5
61	61	311	561	811	13.2	4.5
62	62	312	562	812	13.7	4.5
63	63	313	563	813	14.2	4.5
64	64	314	564	814	14.7	4.5
65	65	315	565	815	15.2	4.5
66	66	316	566	816	15.7	4.5
67	67	317	567	817	16.2	4.5
68	68	318	568	818	16.7	4.5
69	69	319	569	819	17.2	4.5
70	70	320	570	820	17.7	4.5
71	71	321	571	821	18.2	4.5
72	72	322	572	822	18.7	4.5
73	73	323	573	823	1.2	7.5
74	74	324	574	824	1.7	7.5
75	75	325	575	825	2.2	7.5
76	76	326	576	826	2.7	7.5
77	77	327	577	827	3.2	7.5
78	78	328	578	828	3.7	7.5
79	79	329	579	829	4.2	7.5

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
80	80	330	580	830	4.7	7.5
81	81	331	581	831	5.2	7.5
82	82	332	582	832	5.7	7.5
83	83	333	583	833	6.2	7.5
84	84	334	584	834	6.7	7.5
85	85	335	585	835	7.2	7.5
86	86	336	586	836	7.7	7.5
87	87	337	587	837	8.2	7.5
88	88	338	588	838	8.7	7.5
89	89	339	589	839	9.2	7.5
90	90	340	590	840	9.7	7.5
91	91	341	591	841	10.2	7.5
92	92	342	592	842	10.7	7.5
93	93	343	593	843	11.2	7.5
94	94	344	594	844	11.7	7.5
95	95	345	595	845	12.2	7.5
96	96	346	596	846	12.7	7.5
97	97	347	597	847	13.2	7.5
98	98	348	598	848	13.7	7.5
99	99	349	599	849	14.2	7.5
100	100	350	600	850	14.7	7.5
101	101	351	601	851	15.2	7.5
102	102	352	602	852	15.7	7.5
103	103	353	603	853	16.2	7.5
104	104	354	604	854	16.7	7.5
105	105	355	605	855	17.2	7.5
106	106	356	606	856	17.7	7.5
107	107	357	607	857	18.2	7.5
108	108	358	608	858	18.7	7.5
109	109	359	609	859	1.2	10.5
110	110	360	610	860	1.7	10.5
111	111	361	611	861	2.2	10.5
112	112	362	612	862	2.7	10.5
113	113	363	613	863	3.2	10.5
114	114	364	614	864	3.7	10.5
115	115	365	615	865	4.2	10.5
116	116	366	616	866	4.7	10.5
117	117	367	617	867	5.2	10.5
118	118	368	618	868	5.7	10.5
119	119	369	619	869	6.2	10.5
120	120	370	620	870	6.7	10.5
121	121	371	621	871	7.2	10.5

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
122	122	372	622	872	7.7	10.5
123	123	373	623	873	8.2	10.5
124	124	374	624	874	8.7	10.5
125	125	375	625	875	9.2	10.5
126	126	376	626	876	9.7	10.5
127	127	377	627	877	10.2	10.5
128	128	378	628	878	10.7	10.5
129	129	379	629	879	11.2	10.5
130	130	380	630	880	11.7	10.5
131	131	381	631	881	12.2	10.5
132	132	382	632	882	12.7	10.5
133	133	383	633	883	13.2	10.5
134	134	384	634	884	13.7	10.5
135	135	385	635	885	14.2	10.5
136	136	386	636	886	14.7	10.5
137	137	387	637	887	15.2	10.5
138	138	388	638	888	15.7	10.5
139	139	389	639	889	16.2	10.5
140	140	390	640	890	16.7	10.5
141	141	391	641	891	17.2	10.5
142	142	392	642	892	17.7	10.5
143	143	393	643	893	18.2	10.5
144	144	394	644	894	18.7	10.5
145	145	395	645	895	1.2	13.5
146	146	396	646	896	1.7	13.5
147	147	397	647	897	2.2	13.5
148	148	398	648	898	2.7	13.5
149	149	399	649	899	3.2	13.5
150	150	400	650	900	3.7	13.5
151	151	401	651	901	4.2	13.5
152	152	402	652	902	4.7	13.5
153	153	403	653	903	5.2	13.5
154	154	404	654	904	5.7	13.5
155	155	405	655	905	6.2	13.5
156	156	406	656	906	6.7	13.5
157	157	407	657	907	7.2	13.5
158	158	408	658	908	7.7	13.5
159	159	409	659	909	8.2	13.5
160	160	410	660	910	8.7	13.5
161	161	411	661	911	9.2	13.5
162	162	412	662	912	9.7	13.5
163	163	413	663	913	10.2	13.5

Title: TOS Protocol and Procedure: Plant Belowground Biomass Sampling		Date: 05/17/2018
NEON Doc. #: NEON.DOC.014038	Author: C. Meier	Revision: F

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
164	164	414	664	914	10.7	13.5
165	165	415	665	915	11.2	13.5
166	166	416	666	916	11.7	13.5
167	167	417	667	917	12.2	13.5
168	168	418	668	918	12.7	13.5
169	169	419	669	919	13.2	13.5
170	170	420	670	920	13.7	13.5
171	171	421	671	921	14.2	13.5
172	172	422	672	922	14.7	13.5
173	173	423	673	923	15.2	13.5
174	174	424	674	924	15.7	13.5
175	175	425	675	925	16.2	13.5
176	176	426	676	926	16.7	13.5
177	177	427	677	927	17.2	13.5
178	178	428	678	928	17.7	13.5
179	179	429	679	929	18.2	13.5
180	180	430	680	930	18.7	13.5
181	181	431	681	931	1.2	16.5
182	182	432	682	932	1.7	16.5
183	183	433	683	933	2.2	16.5
184	184	434	684	934	2.7	16.5
185	185	435	685	935	3.2	16.5
186	186	436	686	936	3.7	16.5
187	187	437	687	937	4.2	16.5
188	188	438	688	938	4.7	16.5
189	189	439	689	939	5.2	16.5
190	190	440	690	940	5.7	16.5
191	191	441	691	941	6.2	16.5
192	192	442	692	942	6.7	16.5
193	193	443	693	943	7.2	16.5
194	194	444	694	944	7.7	16.5
195	195	445	695	945	8.2	16.5
196	196	446	696	946	8.7	16.5
197	197	447	697	947	9.2	16.5
198	198	448	698	948	9.7	16.5
199	199	449	699	949	10.2	16.5
200	200	450	700	950	10.7	16.5
201	201	451	701	951	11.2	16.5
202	202	452	702	952	11.7	16.5
203	203	453	703	953	12.2	16.5
204	204	454	704	954	12.7	16.5
205	205	455	705	955	13.2	16.5

<i>Title:</i> TOS Protocol and Procedure: Plant Belowground Biomass Sampling		<i>Date:</i> 05/17/2018
<i>NEON Doc. #:</i> NEON.DOC.014038	<i>Author:</i> C. Meier	<i>Revision:</i> F

clipCellNumber subplotID = 31	clipCellNumber subplotID = 21	clipCellNumber subplotID = 23	clipCellNumber subplotID = 39	clipCellNumber subplotID = 41	easting offset	northing offset
206	206	456	706	956	13.7	16.5
207	207	457	707	957	14.2	16.5
208	208	458	708	958	14.7	16.5
209	209	459	709	959	15.2	16.5
210	210	460	710	960	15.7	16.5
211	211	461	711	961	16.2	16.5
212	212	462	712	962	16.7	16.5
213	213	463	713	963	17.2	16.5
214	214	464	714	964	17.7	16.5
215	215	465	715	965	18.2	16.5
216	216	466	716	966	18.7	16.5