

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

TOS PROTOCOL AND PROCEDURE: SOIL PHYSICAL, CHEMICAL, AND MICROBIAL MEASUREMENTS

PREPARED BY	ORGANIZATION	DATE
E. Hinckley	FSU	12/31/2013
J. Parnell	FSU	12/31/2013

APPROVALS	ORGANIZATION	APPROVAL DATE
Mike Stewart	PSE	09/15/2014
Dave Tazik	SCI	07/11/2014

RELEASED BY	ORGANIZATION	RELEASE DATE
Stephen Craft	PSE	09/15/2014

See configuration management system for approval history.

© 2014 NEON Inc. All rights reserved.

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

Change Record

REVISION	DATE	ECO #	DESCRIPTION OF CHANGE
A_DRAFT	10/03/2011	ECO-00280	Initial Draft Release
B_DRAFT	01/13/2014	ECO-01140	Draft release. Will be finalized in next rev.
C	03/25/2014	ECO-01670	Production release, template change, and other changes as detailed in Appendix C
D	09/15/2014	ECO-02086	Minor updates to SOP B (Field Sampling) and SOP C (Lab Processing)

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

TABLE OF CONTENTS

1 DESCRIPTION.....1

1.1 Purpose 1

1.2 Scope..... 1

1.3 Acknowledgements..... 1

2 RELATED DOCUMENTS AND ACRONYMS1

2.1 Applicable Documents 1

2.2 Reference Documents..... 2

2.3 Acronyms 2

2.4 Definitions..... 3

3 BACKGROUND AND OBJECTIVES3

3.1 Background 3

3.2 NEON Science Requirements 4

3.3 NEON Data Products 4

4 PROTOCOL5

5 QUALITY ASSURANCE AND CONTROL6

6 SAFETY7

7 PERSONNEL REQUIREMENTS.....7

8 TRAINING REQUIREMENTS.....8

9 SAMPLE FREQUENCY AND TIMING8

9.1 Sampling Frequency and Timing 8

9.2 Criteria for Determining Sampling Dates 10

9.3 Sampling Frequency..... 10

9.4 Sampling Timing Parameters 10

10 STANDARD OPERATING PROCEDURES.....11

SOP A: Preparing for Sampling 11

SOP B: Field Sampling 12

SOP C: Laboratory Processing and Analyses..... 16

SOP D: Sample Shipment 21

SOP E: Data Entry and Verification..... 23

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

11 REFERENCES24

APPENDIX A QUICK REFERENCES25

APPENDIX B CHECKLISTS26

APPENDIX C PROTOCOL CHANGE SUMMARY.....28

APPENDIX D SAMPLE SHIPPING INFORMATION29

LIST OF TABLES AND FIGURES

Table 1. Approximate sampling dates for soil core sampling at NEON sites..... 9

Table 2. Field equipment list for field sampling one site..... 15

Table 3. Laboratory equipment list for processing soils from one site 20

Table 4. Laboratory equipment list (for shipping samples from one site) 22

Figure 1. Decision Tree 6

Figure 2. Soil profiles from (a) Maryland, (b) Michigan, and (c) Florida..... 8

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

1 DESCRIPTION

1.1 Purpose

The primary purpose of this document is to provide change controlled version of Observatory protocols and procedures for Plot Establishment. This document provides the content for training and field-based materials for NEON staff and contractors. Content changes (i.e. changes in particular tasks or safety practices) occur via this change controlled document, not through field manuals or training materials.

This document is a detailed description of the field establishment process, relevant pre- and post-field tasks, and safety issues as they relate to this procedure and protocol.

1.2 Scope

This document relates the tasks for a specific field sampling and directly associated activities and safety practices. This document does not describe:

- General safety practices
- Site-specific safety practices
- General equipment maintenance

It does identify procedure-specific safety hazards and associated safety requirements such as safe use of required chemicals and reagents.

1.3 Acknowledgements

This protocol is based closely on standard soil sampling methods, as described by the Soil Science Society of America and methods published by the Long-term Ecological Research network (Robertson et al., 1999).

2 RELATED DOCUMENTS AND ACRONYMS

2.1 Applicable Documents

Applicable documents contain information that shall be applied in the current document. Examples are higher level requirements documents, standards, rules and regulations.

AD [01]	NEON.DOC.004300	EHS Safety Policy and Program Manual
AD [02]	NEON.DOC.004316	Operations Field Safety and Security Plan
AD [03]	NEON.DOC.000724	Domain Chemical Hygiene Plan and Biosafety Manual
AD [04]	NEON.DOC.001155	NEON Training Plan
AD [05]	NEON.DOC.050005	Field Operations Job Instruction Training Plan

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

2.2 Reference Documents

Reference documents contain information complementing, explaining, detailing, or otherwise supporting the information included in the current document.

RD [01]	NEON.DOC.000008	NEON Acronym List
RD [02]	NEON.DOC.000243	NEON Glossary of Terms
RD [03]	NEON.DOC.005003	NEON Scientific Data Products Catalog
RD [04]	NEON.DOC.014051	Field Audit Plan
RD [05]	NEON.DOC.000824	Data and Data Product Quality Assurance and Control Plan
RD [06]		EHS USDA Soil Permit SOP
RD [07]	NEON.DOC.000906	TOS Science Design for Terrestrial Biogeochemistry
RD [08]	NEON.DOC.000908	TOS Science Design for Terrestrial Microbial Ecology
RD [09]	NEON.DOC.001403	NEON Raw Data Ingest Workbook for TOS Terrestrial Biogeochemistry: Chemistry of Soils and Plants
RD [10]	NEON.DOC.001577	Datasheets for TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements
RD [11]	NEON.DOC.001271	NEON Protocol: Manual Data Entry

2.3 Acronyms

C	Carbon
¹² C	Common stable isotope of carbon
¹³ C	Less common stable isotope of carbon
Ca ²⁺	Calcium
CaCl ₂	Calcium chloride
cm	Centimeter
mm	Millimeter
DNA	Deoxyribonucleic Acid
g	Grams
h	Hours
² H	Deuterium; the less common stable isotope of hydrogen
K ⁺	Potassium
m	Meter
M	Molar
mg	Milligram
ml	Milliliter
mRNA	Messenger Ribonucleic Acid
N	Nitrogen
¹⁵ N	Less common stable isotope of nitrogen
¹⁴ N	Common stable isotope of nitrogen
PDA	Personal Digital Assistant
PO ₄ ³⁻	Phosphate
P	Phosphorus

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

P&P	Procedure and Protocol
S	Sulfur
SO ₄ ²⁻	Sulfate
USDA	United States Department of Agriculture

2.4 Definitions

A **protocol** is a formal summary description of a procedure and its related rationale, and includes information on knowledge and resources needed to implement the procedure. A **procedure** is a set of prescribed actions that must take place to achieve a certain result, and can also be called a method. It differs from a science design in that science designs provide a more complete description of the rationale for selecting specific protocols. It differs from a training manual in that training manuals provide materials in support of skills acquisition in the topic areas including information on how to best train staff rather than detailing only the steps of the procedure.

3 BACKGROUND AND OBJECTIVES

3.1 Background

This document describes the required protocol for conducting field sampling of and domain lab processing for soil physical properties, nutrient stocks, soil nutrient transformations, and microbial biodiversity and function. We are interested in quantifying the stocks of soil carbon (C) and nutrients to understand ecosystem nutrient status, measuring the isotopic (C and N) composition of the soil to gain a picture of integrated ecosystem processes, quantifying soil nutrient transformations to understand the rates of microbially-mediated processes, and determining the microbial community composition. We will characterize the soil physical and chemical properties, including pH and volumetric water content, which are some of the environmental controls on microbially-mediated biogeochemical processes. As these datasets will be compared with one another, analyses for each component are performed on the same material; we do not collect separate soil cores for microbial measurements and nutrient stocks. The goal is that NEON data will be used to address a variety of questions about biogeochemical cycling at multiple spatial and temporal scales.

Typically, ecosystem stocks of C and N are expressed as mass per unit area (e.g., g C per m²). For soil, this calculation requires knowing the dry mass of soil in a known volume (i.e., bulk density, g per cm³), and the concentration (or amount) of the element per gram of dry soil (e.g., mg per g). Isotopic ratios, the measure of a less common isotope (e.g., ¹⁵N) relative to the most abundant isotope of an element (e.g., ¹⁴N), gives a picture of the integrated ecosystem processes occurring within soils or other media and possibly the source of that element. Commonly, it is expressed as per mil (‰) using the delta (δ) notation. Soil nutrient transformations, such as nitrification, are calculated by comparing initial and final (i.e., T0 and T7 days) extractions of soil nitrate concentrations; they are expressed as mg NO₃⁻ per g dry soil per day.

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

Microbial diversity and the change in microbial community dynamics are measured by sequencing the 16S (Archaea and bacteria) and ITS (fungi) ribosomal DNA gene. This provides information on the members of the microbial community that are present as well as some indication of the relative abundance of each member of the community. The sequence of the total DNA extracted from the soil (metagenome) will provide information on the functional potential of the microbial communities and the sequence of the expressed mRNA genes (metatranscriptome) informs on the active microbial processes occurring in the soil community.

Measurements of soil physical and biogeochemical properties and microbial community dynamics provide scientists, managers, and decision-makers with important information such as whether the ecosystem is retaining or losing nutrients, how water and nutrients move through landscapes, and shifts in microbially-mediated ecosystem processes due to changes in nutrient concentrations. Comparing these data with those from other ecosystem components, including atmospheric deposition, surface water transformations and transport, and above and belowground plant productivity allows investigators to evaluate material fluxes across the landscape. Temporal and spatial considerations involved in sampling will provide data that can be used to address how the ecosystem is changing over time, as well as in response to climate shifts or land use/land cover change at local, regional, and continental scales. For example, changes in precipitation patterns can alter wetting and drying cycles within the soil matrix. Such changes to the soil matrix will likely affect microbial activity, the redox behavior of the soil, and transport of chemical constituents from land to surface waters.

The following protocol outlines the field and laboratory procedures required to collect, process, and maintain integrity of soil samples collected during Field Operations. It includes detailed guidance for locating sites, collecting soil cores and field-associated metadata, field and laboratory processing of soil cores, and storage and shipment of samples to analytical laboratories or archives.

3.2 NEON Science Requirements

This protocol fulfills Observatory science requirements that reside in NEON’s Dynamic Object-Oriented Requirements System (DOORS). Copies of approved science requirements have been exported from DOORS and are available in NEON’s document repository, or upon request.

3.3 NEON Data Products

Execution of this protocol procures samples and/or generates raw data satisfying NEON Observatory scientific requirements. These data and samples are used to create NEON data products, and are documented in the NEON Scientific Data Products Catalog (RD [04]).

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

4 PROTOCOL

The field protocol used by NEON for collecting soil cores to analyze physical properties, biogeochemistry, and microbial communities follows the protocols presented in the Soil Science Society of America Methods of Soil Analysis texts (Sparks et al., 1996; Dane and Topp, 2002), as well as the Standard Soil Methods for Long-Term Ecological Research (Robertson et al., 1999). Soils are inherently spatially heterogeneous, and, thus, several samples must be collected in order to capture variability at multiple length scales (e.g., soil core, sub-plot, plot, site). Plot locations in which soil samples will be collected vary for each NEON site; this information will be provided as a job ticket each year to domain managers and field personnel. In addition, soil core coordinates will be randomly generated within each plot. For each soil sampling location, staff scientists will provide field crews with x, y coordinates originating from the southwest corner (i.e., the reference point) of each plot. In many cases, multiple cores per sampling location must be collected and pooled into a composite sample, both to obtain enough material for analysis and to generate a representative sample at the soil core (i.e., centimeter to meter) scale.

Soil types and horizons differ throughout the 20 NEON domains. When an organic and mineral horizons are present within a single core they will be separated prior to analysis. However, other horizons will not be separated (e.g., A and Bw).

In addition, the depth of soil to saprolite or bedrock will vary across domains. NEON soil sampling shall sample to a maximum depth of 30 cm where possible. More detailed characterization of the dominant soil type will occur during the construction period of NEON, including thorough description of soil pits dug from the surface to bedrock (where possible) at all core and relocatable sites. The Fundamental Instrument Unit (FIU) team will carry out this activity.

It is critical that the locations from which soil samples are collected have not been disturbed prior to sampling. Examples of disturbance include prior sampling, compaction, and contamination atypical of the site (urban and agricultural sites). Other factors that may necessitate relocation of sampling efforts include: obstruction by tree roots, large (i.e., > 8 cm) rocks, or holes (e.g., from small burrowing mammals). In any of the above scenarios, field personnel should note the impediment in the PDA and/or field data sheet, seek a new location as close as possible to that of the predetermined sampling location, and note the new sampling location in the PDA and/or field data sheet. Once soil cores have been collected, extraction holes must be backfilled as per local permit regulations and the final sample location recorded so that subsequent samples are not collected in the same locations.

No processing is required in the domain laboratory for microbial samples.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinkley	Revision: D

5 QUALITY ASSURANCE AND CONTROL

The procedures associated with this protocol will be audited according to the Field Audit Plan (RD [04]). Additional quality assurance will be performed on data collected via these procedures according to the NEON Data and Data Product Quality Assurance and Control Plan (RD [05]).

When unexpected field conditions require deviations from this protocol, the following field implementation guidance must be followed to ensure that quality standards are met:




Figure 1. Decision Tree

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

6 SAFETY

Personnel working at a NEON site must be compliant with safe field work practices as outlined in the Operations Field Safety and Security Plan (AD [02]) and EHS Safety Policy and Program Manual (AD [01]). Additional safety issues associated with this field procedure are outlined below. The Field Operations Manager and the Lead Field Technician have primary authority to stop work activities based on unsafe field conditions; however, all employees have the responsibility and right to stop their work in unsafe conditions.

Work that involves disturbance of soils or plant litter may increase the concentration of fungal spores in the air. Take precautions to prevent inhalation of dust from potentially contaminated soils and plant litter. Review zoonotic diseases in AD [02] for information on areas of high risk and symptoms of fungal infection.

In order to protect against the spread of potential plant pathogens or unwanted pests, transportation of quarantined soils requires a USDA soil permit and special treatment of stored or discarded soils. Protocols for the handling of quarantined soils can be found in NEON’s USDA Animal and Plant Health Inspection permit (RD[13]). Domains or sites with soils that require quarantine can be found in [7 CFR Part 301 Domestic Quarantine Notices of the Plant Protection Act \(7 U.S.C. 7756\)](#). Quarantine soil samples that are being shipped to external laboratory facilities must include a copy of the USDA Soil Permit (and comply with outlined shipping guidelines) from the contracted facility. The protocol for including this permit is described in detail in this document.

Soil sampling equipment can be sharp and/or heavy (i.e., hori hori knife, slide hammer corer). Please take precautions to handle these tools with appropriate care. In addition, dry ice used for preserving microbial samples must be handled with appropriate safety protection and must never be stored in airtight containers. Shipment of samples to external laboratory facilities on dry ice requires additional safety labels.

7 PERSONNEL REQUIREMENTS

Soil types and profile characteristics differ greatly across the NEON domains (see examples in Figure 2). When sampling soil, field personnel must be familiar with the basic characteristics of a typical soil profile at the local NEON site, such as ability to differentiate between organic and mineral horizons and be familiar with typical soil depth. For example, in Domain 1, this would include understanding differences among the leaf litter (loose vegetal matter that may be intact or partially shredded), organic horizon (often dark and slightly sticky, with pieces of vegetal matter in various stages of decomposition) and mineral horizons (little vegetal matter, primarily accumulated minerals). The NEON protocol requires removing the litter layer, and sampling the organic and mineral soil horizons separately. Other locations, such as Domain 10, an organic horizon may not exist, but other features (e.g., a plow horizon, shallow soils) may be present. Field personnel should be prepared to take extensive notes on any

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

anomalous soil features that they observe when sampling, or in-field decisions that they make in order to carry out this protocol.




Figure 2. Soil profiles from (a) Maryland, (b) Michigan, and (c) Florida. (Source: Dr. Ray Weil, University of Maryland (a and b) and the University of Florida (c), <http://soil.gsfc.nasa.gov>).

8 TRAINING REQUIREMENTS

All technicians must complete required safety training as defined in the NEON Training Plan (AD [04]). Additionally technicians complete protocol specific training for safety and implementation of protocol as required in Field Operations Job Instruction Training Plan (AD [05]).

Field personnel are to be trained in use of the soil corer, identifying and differentiating local soil horizons, using dry ice for sample preservation and transport, practicing clean laboratory techniques, making salt solutions in the laboratory for pH analysis, and safe working practices for field sampling.

9 SAMPLE FREQUENCY AND TIMING

9.1 Sampling Frequency and Timing

The timing, frequency, and extent of soil sampling constitute “the science design” (see (RD [07]) and (RD [08]) and vary by NEON domain or site. The timing of sampling allows researchers to assess terrestrial biogeochemical cycles within a particular window, and, therefore, timing depends on the dominant drivers that affect microbial communities, as well as nutrient stocks and fluxes in ecosystems. These drivers include, but are not limited to, climate forcing (e.g., solar radiation, air and soil temperature, and precipitation), disturbance (e.g., ice storms, wildfire, land use/land cover change), and plant phenology (e.g., dormancy, begin physiological activity, peak plant productivity, senescence). The frequency of sampling allows researchers to investigate how microbial communities and nutrient dynamics change within and between seasons or years; for example, at Domain 1, soil respiration will be at its minimum during winter and maximum during summer, so one might choose to sample during the peak and trough of this cycle. Finally, the extent of soil sampling allows researchers to evaluate the spatial heterogeneity

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinkley	Revision: D

of nutrient stocks and fluxes; differences in soil type, plant communities, or hillslope aspect will affect the results, so these features are taken into account in the spatial component of the sampling design. Thus, at the different NEON sites, sampling will occur more or less frequently, and to a greater or lesser extent, depending on the climatic factors and landscape features, the biogeochemical context of the location (e.g., is this an area of high N loading?), as well as logistical (e.g., site accessibility) and financial constraints.

Of the measurements made as part of NEON soil sampling efforts, nutrient and microbial dynamics will change more frequently than soil physical properties; hence, these collections follow different schedules. For the first 1-2 years, sampling will occur in a subset of four plots each month when the ground is not frozen to determine seasonal variation (specific plots provided in site-specific appendix). After 2 years, sampling will occur in up to 10 plots 3 times each year.

We estimate that one soil sampling bout per site requires 2 technicians for 1-5 days, plus travel to and from the site, and sample processing, including root and rock removal, sample homogenization, sieving (if required), and sample shipment.

Table 1. Approximate sampling dates for soil core sampling at NEON sites Note: monthly samples are used for microbial analyses only; biogeochemical analyses will be conducted on the soil cores taken during the growing season *during years these analyses are scheduled*.

Domain	Estimated Dates	Frequency ¹
1	April 1 – Jan 1	Monthly
2	March 1 – Jan 1	Monthly
Domain	Estimated Dates	Frequency ¹
3	Jan 1 – Dec 31	Monthly
4	Jan 1 – Dec 31	Monthly
5	April 1 – Jan 1	Monthly
6	March 1 – Jan 1	Monthly
7	March 1 – Jan 1	Monthly
8	Jan 1 – Dec 31	Monthly
9	April 1 – Jan 1	Monthly
10	March 1 – Jan 1	Monthly
11	Jan 1 – Dec 31	Monthly
12	April 1 – Jan 1	Monthly
13	March 1 – Jan 1	Monthly
14	Jan 1 – Dec 31	Monthly
15	March 1 – Jan 1	Monthly
16	Jan 1 – Dec 31	Monthly
17	Jan 1 – Dec 31	Monthly

¹ Sampling occurs monthly when ground is not frozen/snow-covered, estimated dates provide general guidance of when each domain can expect ground to be suitable for sampling. Verify whether ground is frozen or not each month based on local conditions.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

18	April 1 – Oct 1	Monthly
19	April 1 – Oct 1	Monthly
20	Jan 1 – Dec 31	Monthly

9.2 Criteria for Determining Sampling Dates

Sampling dates will be determined by NEON staff scientists and domain Field Operations staff for each sampling year. Communication will be via phone, email, and JIRA.

9.3 Sampling Frequency

Sample once during the growing season (e.g., during July) for biogeochemical analyses, if these samples are being done in the sampling year. Sample monthly (Unless NEON staff scientist specifies differently, using a JIRA ticket), except when ground is frozen, for microbial analyses for the first 2 years. Following the first 2 years, sampling frequency will be 3 times per year with timing provided as domain-specific job tickets.

9.4 Sampling Timing Parameters

Sampling bouts should be approximately 25-35 days apart for soils collected for microbial analyses, unless NEON staff scientists specify differently at the beginning of the field season. Subsamples for microbial analyses and biogeochemical analyses are from the same sample (i.e., core or composite sample of multiple cores), so these collections occur simultaneously.

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

10 STANDARD OPERATING PROCEDURES

SOP A: Preparing for Sampling

- 1) Fill out site information on field datasheet, located in Datasheets for Field and Lab Protocol: Soil Physical, Chemical, and Microbial Measurements (RD [10]). Make sure to use proper formats, as detailed in datasheets and described by domain managers. For example, eventDate (YYYYMMDD) and eventTime fields must be recorded based on 24 h with no colon (e.g. 1830). Print cryovial labels with sampleID and eventDate (changes in coordinates should be reprinted and applied as a new label upon return to domain laboratory) for 50 ml vial microbe samples.
- 2) If applicable, based on job ticket: “Cold-soak” coolers for shipment: 24 h prior to anticipated shipment time, place open shipping coolers with ice packs into a freezer. These will be used for shipping field-moist soils.
- 3) Prior to sample collection, plots and subplots where soil samples will be collected should be identified and marked.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinkley	Revision: D

SOP B: Field Sampling

Identify the plot:

- 1) Navigate to the southwest corner of the plot where sampling is to occur.
- 2) Lay out meter tapes on the west and south sides of the plot.
- 3) Find the sampling location(s) using the tapes as guides for the given x, y coordinates.
- 4) Put on a clean pair of powderless gloves (you only need 1 pair per random sampling location to take the cores that constitute a sample, but you MUST put on a new pair at each location—between samples—do not reuse gloves).

Measure soil temperature:

- 1) At each sampling location where you take soil core(s), take one soil temperature reading.
- 2) Remove the litter layer and carefully insert temperature probe into the soil (10 cm). Don't force the probe as they break easily.
- 3) Allow probe to equilibrate (~2 min) before recording the value in degrees C in the field datasheets. Do not make measurement with sun directly onto probe (you can shade it with your body, if necessary).

Collect soil core:

- 1) Identify the first soil core sampling location. Always core vertically, not perpendicular, when collecting on a slope. Measure the depth of the litter layer (cm) above each core location and record the value. This can be measured using a ruler; remove litter layer and measure profile depth of undisturbed litter layer over soil. Be careful not to compact the litter layer where you are taking your measurement.
- 2) Push the litter layer away from where you are going to core into the soil surface. The litter layer is general composed of undecomposed plant material (e.g. leaves are still recognizable), whereas an organic horizon will contain organic material in various states of decomposition.
- 3) If an **organic horizon** is present, conduct steps 4-5. If not, skip to step 9.
- 4) Cut out an organic horizon "brownie" using the square frame cutter tool. Measure the depth of each side and record the average value in cm.
- 5) Repeat steps 2-4 at up to two other locations within 0.5 m of the first location if more material is needed (this will be specified in the current year's job ticket/sample list). The three locations form one composite sample. Put the organic horizon samples into a 1 gallon resealable plastic bag and homogenize by hand.
- 6) Fill a 50 ml vial with homogenized organic horizon material from the resealable plastic bag for microbial analysis. The remaining contents in the resealable plastic bag are for physical/elemental/isotopic analysis.
- 7) Label each bag/vial with the sampleID, plotID, subplotID, coreCoordinateX, coreCoordinateY, eventDate, horizon, measuredBy (technician name), and recordedBy (technician name).

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

- 8) Place the microbial sample in the cooler with dry ice, and the physical/elemental/isotopic sample into a cooler with ice packs.
- 9) Collect up to three **mineral horizon** cores per sample location using the slide hammer corer or other coring device. If significant obstructions such as rocks are present, another approved device may be used to get the soil out of the ground.
 - a) If collecting solely for microbial diversity measurements (and pH), collect one core. Can be collected using a device other than slide hammer corer as long as the sample is a representative core to 30 cm.
 - b) If collecting for soil microbial diversity and biogeochemistry, collect up to three cores in order to get enough material to complete all domain and contract laboratory measurements.
 - c) The slide hammer corer **MUST** be used for the bulk density core.
- 10) If organic horizon was present, take cores from the locations where you collected organic horizon brownies. Core down so that the total depth of the soil core (organic + mineral soil) is maximum of 30 cm as measured in the soil core hole, not the extracted soil core, which can become compacted.



A piece of masking or lab tape can be placed on the outside of the corer to indicate the depth to stop driving the corer into the mineral soil horizon.

- 11) If an organic horizon is not present, core 30 cm of mineral soil. If the soil depth is < 30 cm or there are significant impediments to coring (e.g., roots and rocks throughout the site or depth to saprolite is < 30 cm), core to the depth you are able and make a note in the 'commentsCollection' field of the datasheet.
- 12) Place all mineral soil cores collected from the sample coordinates into the same resealable plastic bag.
- 13) Break up the cores and homogenize (mix) in the bag with your gloved hand.
- 14) Fill a 50 ml vial to the top with homogenized mineral soil.
- 15) Label the vial and the resealable plastic bag with the sampleID, plotID, subplotID, coreCoordinateX, coreCoordinateY, eventDate, horizon, measuredBy (technician name), and recordedBy (technician name).
- 16) Put the bag in the cooler with the ice packs, and immediately place the vial in the cooler with dry ice (mRNA changes very quickly).
- 17) Enter the metadata in field datasheet.
- 18) Thoroughly rinse sampling equipment (corer, thermometer, bulb planter, etc).
- 19) Remove gloves and stow in a dedicated trash bag.
- 20) Repeat all steps for additional sampling locations.

Collect soil core for bulk density:

- 1) If required in the job ticket, take a soil core for bulk density
- 2) Measure the litter layer in the sampling location specified by the job ticket and record depth in datasheet.

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

- 3) Remove the litter layer.
- 4) Collect an organic horizon brownie, note the average depth, and place it in a resealable plastic bag.
- 5) Label the bag as in step #15 (Collect soil core) with the addition of “bulkDensity” on the bag and place the organic soil inside. Put the sample in the cooler with the ice packs.
- 6) Use the slide hammer corer (this tool is required for bulk density measurements) to take a core of the mineral soil (to a total borehole—organic AND mineral horizon—depth of 30 cm) and place in a bag labeled as above, with the addition of “bulkDensity”.
- 7) Write the total length of the core in the datasheet (or PDA) and field notebook, bag this core, and label the bag as above with the addition of “bulkDensity” on the bag. Place in the cooler with the ice packs.

Sample transport:

- 1) Keep soils for biogeochemistry analysis in the cooler with the ice packs and transfer to 4 C refrigerator upon return to domain lab.
- 2) Keep soils for microbial analysis in the cooler with the dry ice and transfer to ultralow freezer upon return to domain lab.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

Field Equipment and Materials

Table 2. Field equipment list for field sampling one site

Suggested (S) /Required (R)	Maximo Number	Item Description	Quantity	Habitat-Specific	Special Handling
(RD [10])		Field datasheets	---	N	N
S		Hard copy of job ticket for soil collection (i.e., information about plots to sample, random soil coring locations)	1	N	N
S		Survey flags	3	N	N
Required	MX105087	Ice packs, -20C	16 (+)	N	N
Required	MX100212	Dry ice	20 pounds	N	Y
Required		Coolers	2	N	N
Required	MX103483	Slide hammer corer (for bulk density)	1	N	N
S		Bulb planter	1	N	N
S		Flexible trays for sample processing in field	2	N	N
S		Ruler	1	N	N
Required		Meter tapes	2	N	N
S		Trowel	1	N	N
S		Ruler	1	N	N
S		Hori hori knife	1	N	N
S		Organic horizon cutter template	1	Y	N
Required	MX103206	Field thermometer	2	N	N
Required	MX100645; MX100646; MX100647; MX100644	Powderless gloves	1 box	N	N
Required	MX100592	Ziploc freezer resealable plastic bags (gallon)	2 boxes	N	N
Required		50 ml vials	50	N	N
Required	MX104432	Cryogenic vial labels	50	N	N
S		Disposable paper tissues or cloth	1 box or 2 cloths	N	N
Required	MX102002	Permanent markers	3	N	N
S		Pencils	4	N	N
S		PDA	1	N	N
Required	MX100308	DI water	2 liters	N	N
S		Trash bag	2	N	N

*Suggested indicates that a suitable alternative is acceptable (e.g. field datasheets unless PDA is available).

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

SOP C: Laboratory Processing and Analyses

Directions are written for field-moist, air-dried, and oven-dried processing of soils. These different processing approaches pertain to different analyses, described below. In all cases, conduct work on a clean lab bench space that has been wiped with ethanol prior to processing samples. Samples for microbial analysis do not require further processing in the domain facility. They should be shipped as soon as possible within 24 hours to the contracted laboratory(ies) (see SOP D and appendix D), but shipment may be delayed up to 3 days for microbial samples (per Appendix B, checklist2).

Part 1: Analyzing subsamples for moisture content

Analysis of the moisture present in the soil is important for understanding the field conditions experienced by soil microbial communities, and for some soil nutrient calculations. Conduct the following steps to generate soil moisture data for each horizon of each soil sample. Record the necessary metadata and values in Lab Datasheet: Measuring Soil pH and Moisture (in (RD [10])). Soil moisture analysis should be done within 24 h of field collection. In cases where domain staff are working at remote sites, keep samples on fresh ice packs in coolers and process immediately upon return to the domain facility lab.

- 1) Wear powderless gloves. Use a new glove for each soil sample (Suggestion: use one hand to handle the sample so that you only have to replace one glove. If you use two hands, replace both gloves.).
- 2) Label foil weighing boat with sampleID and weigh foil boat to nearest 0.01 g and record value in the datasheet.
- 3) Place 5 g of a field moist organic horizon sample (not sieved) or 10 g of a field moist mineral horizon sample (not sieved) into the weighed foil weighing boat. Record weight to nearest 0.01 g.
- 4) Repeat Steps 1-3 for all horizon samples.
- 5) Place all samples into drying oven (recommended on a cafeteria tray) at 105°C for 48 h. Record time in oven on datasheet.
- 6) At conclusion of drying period, immediately weigh dried sample + weighing boat to nearest 0.01 g and record values in the datasheet. Also record the date and time out of oven.
- 7) Dispose of soils according to permit requirements and keep all foil weighing boats that are clean and undamaged for reuse.

Part 2: Sieving and subsampling

- 1) Process samples within 24 h of field collection. In cases where technicians are working remotely, keep samples in coolers on cold ice packs until at the domain lab, and then process immediately.
- 2) Wear powderless gloves. Use a new glove for each soil sample (Suggestion: use one hand to handle the sample so that you only have to replace one glove. If you use two hands, replace both gloves.).
- 3) With gloved hand, stir soil sample to homogenize (mix), breaking up any soil clods completely. At the same time, remove rocks, roots, leaves, and debris. Rocks, roots, leaves, and debris can be discarded according to permit requirements.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

- 4) If sample is **organic horizon**, skip to Step 8 (do not sieve).
- 5) Shake **mineral horizon** samples through a series of sieves, the smallest being 2 mm screen diameter sieve (this will allow all particles ≤ 2 mm to pass through to the collection pan, meeting the standard classification of "soil"). If the sample is too clayey to pass through the sieve, submit a jira ticket to receive further instruction.
- 6) Discard particles > 2 mm according to permit requirements.
- 7) Record on the Lab Datasheet: Post-field Soil Processing: the metadata (site, eventDate, measuredBy (technician name), plotID, subplotID, coreCoordinateX and coreCoordinateY, sampleID, and horizon) and the sieveDate and sieveTime.
- 8) If the current year's job ticket specifies that a subsample of soil is being shipped **field moist** to one or more contracted laboratories, take the specified subsample from the sieve (mineral horizon) or field bag (organic horizon) and place in a quart-sized resealable plastic bag labeled with metadata above (step 7). Skip to SOP D for directions about shipping.
- 9) Subsample organic horizon sample (not sieved) and mineral horizon sample (sieved) in order to **oven-dry** for nutrient/isotopic analysis: fill a 18 ml scintillation vial with each unique sample. Transfer sample information to scintillation vial (Suggestion: write sample information on lab tape and wrap tape completely around middle of scintillation vial.). Do not cap vials.
- 10) Place open scintillation vials into the scintillation vial box, which holds 100 vials. Oven-dry at 60°C for 48 hr. Record start and end time in lab processing datasheet. When drying period is complete, cap vials and ship to contracted laboratory for analysis (see SOP D).
- 11) Air-drying samples for pH analysis and archiving: place all remaining sample (your organic horizon samples will be in the field resealable plastic bags, and the mineral soil samples will be coming out of the sieve) into individual paper lunch bags labeled with the metadata above.
- 12) Leave the bag open to air-dry on a clean lab bench or table, away from other activities that might disturb samples. Shake up soil to expose new surfaces once or twice each day. Record startDate and startTime of air-drying in the lab datasheet and track the change in weight according to the appropriate fields in the datasheet.
- 13) Air-drying soil can take several days depending on the initial moisture content. Do not continue with processing until soils are completely dry. Soils are considered completely dry when the change in weight is less than 5% over a 48h period.
- 14) At the conclusion of air-drying samples, a subsample will be analyzed in the domain facility for pH, and ~200 g of the remaining material should be placed into a labeled quart-sized resealable plastic bag, sealed, and stored in a dry cabinet prior to shipment to an archiving facility. For shipment instructions, see SOP D.

Part 3: Analyzing subsamples for pH

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinkley	Revision: D

Soil pH is measured by domain staff on air-dried subsamples. Soil pH is measured potentiometrically in a supernatant liquid that is in equilibrium with a soil suspension of a 1:2 soil-to-liquid (weight/weight) mixture for mineral soils and a ratio of 1:4 for organic soils. Samples are analyzed both in 0.01 M calcium chloride (CaCl_2) and deionized (DI) water and values are recorded in the Lab Datasheet: Measuring Soil pH and Moisture (in (RD [10])).

- 1) Wear gloves throughout this procedure. If you do not touch the soil samples directly, you do not need to change gloves between samples.
- 2) Make the 0.01 M CaCl_2 solution: dissolve 2.94 g of $\text{CaCl}_2 \cdot 2\text{H}_2\text{O}$ in 2 liters of DI water. Note: this solution is stable for approximately 1 year, kept at room temperature out of direct sunlight.
- 3) Check pH of CaCl_2 solution; it should be between 5.0 and 6.5.
- 4) Adjust one drop at a time with concentrated 6N $\text{Ca}(\text{OH})_2$ or 10N HCl if needed (rarely is).
- 5) Weigh out a subsample of air-dried organic or mineral (fraction ≤ 2 mm) soil and place into 50 – 100 mL cup. Use 10 g for mineral soil and 5 g for organic soil.
- 6) Add 20 mL of CaCl_2 solution. DO NOT STIR. (For measuring pH using water, add 10 mL deionized water).
- 7) Allow soil to absorb CaCl_2 solution.
- 8) Thoroughly stir for 10 seconds with a glass rod or plastic stir stick.
- 9) Further stir suspension (for 10 seconds) every 5 minutes for the next 30 minutes.
- 10) Allow suspension (i.e., the flocculated soil) to settle undisturbed for 30 – 60 minutes. (This will vary by soil type. Look for soil materials to be completely saturated by the solution—see next step.)
- 11) Look for supernatant (liquid without precipitate) above the flocculated soil. IF not present, then add another aliquot (20 mL) of CaCl_2 solution and repeat stirring and settling (steps 6 through 8).
- 12) Calibrate the pH meter electrode with pH buffers 4, 7, and 10 according to the manual for the probe.
- 13) Rinse the electrode with deionized water and dry it between buffers.
- 14) Measure pH of supernatant solution, taking care to NOT disturb the flocculated soil.
- 15) Allow reading to stabilize (usually about 1 minute) and record pH value in on datasheet.
- 16) Clean electrode: rinse thoroughly 2 to 3 times with deionized water and gently dry with a fresh lab tissue.
- 17) Repeat steps 5 through 16 for each sample.
- 18) Select 5 soil samples from the group just measured for duplicate (i.e., “Dup”) pH measurement. (Choose soil samples that have ample leftover material.)
- 19) Repeat steps 5 through 16 for the selected five.
- 20) If the original and duplicate subsamples differ by ≥ 0.5 in their pH reading, take a third pH reading. Record all original and duplicate values as separate entries in the data ingest.
- 21) Steps 1-19 describe the procedure for analysis of pH in 0.01 M CaCl_2 . Repeat Steps 5-20, analyzing subsamples in 20 mL deionized water instead of CaCl_2 .

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

Part 4: Processing bulk density samples

If the job ticket specified soil sample collection included collection for bulk density analysis, you will have a set of soil cores that must be processed as follows. Use the Lab Datasheet: Measuring Bulk Density (in (RD [10])).

- 1) Wear powderless gloves, but you DO NOT have to change gloves for each bulk density sample; you can process a whole set of samples with same pair of gloves.
- 2) Take a pre-processing weight of your collected soil bulk density samples: for each organic and mineral horizon sample, tare the scale using a clean, empty resealable plastic bag of the same size that you used in the field. Weigh each organic and mineral soil sample (plus its bag) and record the weight in the datasheet in 'bulkDensWtPresieve (g)'.
- 3) **Organic horizon** samples (if collected at your site) do not need to be sieved. Transfer to a paper paper lunch bag and label that bag with sample metadata from resealable plastic bag (field collection).
- 4) Sieve **mineral horizon** soils through 2mm sieve and place the $\leq 2\text{mm}$ and $> 2\text{mm}$ fractions in separate labeled paper paper lunch bags. Clean materials and sieve using 70% ethanol and water between each sample.
- 5) Place all samples (in their open, labeled paper lunch bags) and 5 empty paper lunch bags into an oven at 105°C for 48 hrs. You only have to dry and weigh one group of 5 paper lunch bags per batch of samples you process.
- 6) Once soil samples are dry, weigh each bag of sample separately and record the values to the nearest 0.01 g in the datasheet. Discard the material in accordance with permit requirements when weights have been obtained accurately (Note: if samples were collected from a quarantine area and processed in non-quarantine lab, disposal of soils, and water used to wash sieves must follow guidelines in the USDA soils permit).
- 7) Record the average weight (to the nearest 0.01 g) of the 5 empty paper lunch bags corresponding to the oven-dried batch of samples in the lab datasheet.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

Laboratory Equipment and Materials

Table 3. Laboratory equipment list for processing soils from one site

Suggested (S) /Required (R)	Maxomo Number	Item Description	Quantity	Condition-Specific	Special Handling
Required	MX100645; MX100646; MX100647; MX100644	Powderless gloves	1 box	N	N
Required	MX103208	Sieves	1 set	N	N
Required	MX100592 MX100593	Resealable plastic bags (gallon and quart sizes)	1 box each	N	N
Required	MX105089	Paper (e.g., "lunch") bags	50	N	N
Required	MX103233	Coin envelopes	1 box	N	N
Required		18 ml plastic scintillation vials	1 box	N	N
Required		Foil weighing boats	50 (+)	N	N
S		Cafeteria trays	4 (+)	N	N
S		50-100 mL cups	50 (+)	N	N
S		2 liter glass volumetric	1	N	N
Required	MX105810	CaCl ₂ ·2H ₂ O	2.94 g	N	N
Required	MX100308	Deionized water	---	N	N
Required	MX105812	HCl	1 ml	N	N
Required	MX105811	Ca(OH) ₂	1 ml	N	N
S		Stir rod	1	N	N
Required		pH meter	1	N	N
Required	MX100583 MX100584 MX100052	pH buffers (4, 7, 10)	1	N	N
(RD[10])		Physical copy of Datasheets for Field and Lab Protocol: Soil Physical, Chemical, and Microbial Measurements	---	N	N

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

SOP D: Sample Shipment

Soil samples shall be shipped according to the USDA Soil Permit requirements: A copy of the receiving laboratory's USDA Soil Permit must be included with foreign soil shipments. A copy of the PPQ form 519 (Compliance agreement) must be included with domestic regulated shipments. The soil permit and appropriate PPQ form must be clearly affixed to the outside of the container. Shipment of permit-requiring samples is restricted only to analytical labs or archive facilities that hold a USDA soils permit. Ship samples immediately following processing steps (i.e., within 24 h). Samples that have been air-dried or oven-dried prior to shipment do not "expire", but to decrease build-up of samples in the domain facility, it is better to ship quickly so that samples are not lost or damaged. However, if there is an issue with receiving contracted laboratory being able to accept samples (e.g., contract not established, problem with soil permit), the shipment may have to be held back. In this case, please submit a Jira ticket.

Part 1: Shipping oven-dried samples for analysis of nutrients and isotopes

- 1) Take scintillation vial box containing processed samples out of the cabinet for shipment.
- 2) Wrap the box in bubble wrap and tape securely, then place in a FedEx box for shipment.
- 3) Include a copy of the USDA soil permit from the contracted laboratory in the box and affix any labels required by the permit, if necessary.
- 4) Include cover letter explaining shipment, and spreadsheet detailing sample inventory (these forms supplied for each specific contract by NEON Headquarters staff).
- 5) Address shipping label appropriately and ship ground.

Part 2: Shipping field moist samples for analysis of nutrients and isotopes

- 1) Use a "cold-soaked" shipping cooler (or coolers, in order to accommodate samples surrounded by ice packs on four sides).
- 2) Fill cooler with securely double-freezer-bagged field-moist soils
- 3) Include a copy of the USDA soil permit from the contracted laboratory in the box and affix any labels required by the permit, if necessary.
- 4) Include cover letter explaining shipment, and spreadsheet detailing sample inventory (these forms supplied for each specific contract by NEON Headquarters staff).
- 5) Address shipping label appropriately and send overnight service with "before COB next day" designation. Do NOT ship on Friday or day before holiday.

Part 3: Shipping air-dried samples for archiving

- 1) Line a thick-walled box (sized to accommodate sample shipment load) with a trash bag.
- 2) Pack samples (in freezer resealable plastic bags) securely within the box. Make sure that air is out of all the bags. Fill all open spaces around samples with packing material.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

- 3) Include a copy of the USDA soil permit from the contracted laboratory in the box and affix any labels required by the permit, if necessary.
- 4) Include cover letter explaining shipment, and spreadsheet detailing sample inventory (these forms supplied for each specific contract by NEON Headquarters staff).
- 5) Address shipping label appropriately and ship ground.

Part 4: Shipping ultra-cold samples for microbial analysis

- 1) Take samples from the ultralow (-80°C) freezer for shipment.
- 2) Immediately place samples in a sturdy insulated shipping container with a minimum 20 lbs of dry ice.
- 3) Seal container to preclude spillage (but make sure it is not air-tight).
- 4) Complete dry ice shipping label.
- 5) Include a copy of the USDA soil permit from the contracted laboratory in the box and affix any labels required by the permit, if necessary.
- 6) Include cover letter explaining shipment, and spreadsheet detailing sample inventory (these forms supplied for each specific contract by NEON Headquarters staff).
- 7) Address shipping label appropriately and send the samples priority overnight mail with tracking number. Do NOT ship on Friday or day before holiday.

Laboratory Equipment and Materials

Table 4. Laboratory equipment list (for shipping samples from one site)

Suggested (S) /Required (R)	Maximo Number	Item Description	Quantity	Habitat-Specific	Special Handling
Required	MX100212	Dry ice	20 pounds	N	Y
Required	MAT111	Dry ice packing labels	1	N	N
Required	MX105087	Ice packs	16 (+)	N	N
Required		Packing tape	1	N	N
Required	MX102297	Foam Cooler	1	N	N
S		USDA Soil Permit from contracted facility(ies), including an necessary labels specified in the permit (see Safety section)	1 per box	N	N
Required		Cover letters and sample inventory spreadsheets for contracted facility(ies). These forms supplied by NEON Headquarters Staff to Domain managers.	1 per box	N	N
S		Boxes	2 (+)	N	N

<i>Title:</i> TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		<i>Date:</i> 09/15/2014
<i>NEON Doc. #:</i> NEON.DOC.014048	<i>Author:</i> E. Hinckley	<i>Revision:</i> D

SOP E: Data Entry and Verification

Data entry and verification are specified in the NEON Protocol: Manual Data Transcription (RD [11]), Data entry, from hardcopy data sheets into electronic data ingest files, must occur within 14 days of data generation. Data ingest file pertaining to this protocol is the NEON Raw Data Ingest Workbook for TOS Terrestrial Biogeochemistry: Chemistry of Soils and Plants (RD [09]). Please take care to check your work (i.e., verify that hardcopy and electronic copy match) and to resolve any data issues that occurred in the field or laboratory that may result in data quality issues as you are going through the values at this time. Specific instructions on where to save/store completed data ingest files, and where and how to back-up and store hardcopy datasheets can be found in RD [11]. .

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

11 REFERENCES

Dane, J.H., and G.C. Topp (Eds). 2002. *Methods of Soil Analysis, Part 4: Physical Methods*. Soil Science Society of America, Madison, WI. 1692 pp.

Sparks, D.L., A.L. Page, P.A. Helmke, R.H. Loeppert, P.N. Soltanpour, M.A. Tabatabai, C.T. Johnston, and M.E. Sumner (Eds). 1996. *Methods of Soil Analysis, Part 3: Chemical Methods*. Soil Science Society of America, Madison, WI. 1390 pp.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

APPENDIX A QUICK REFERENCES

QUICK REFERENCE 1: COLLECTING QUALITY SOIL SAMPLES FOR BIOGEOCHEMICAL ANALYSIS

STEP 1 - Cold soak coolers for microbial samples before going into field.

STEP 2 - Use plot ID and relative (X,Y) coordinates to locate pre-determined sample locations.

STEP 3 - Measure litter layer.

STEP 4 - Collect 3 (for a composite sample) organic horizon sample with “brownie cutter”

STEP 5 – Put organic samples into 1 bag, homogenize, and fill a 50 ml vial. Label bag and vial: store vial on dry ice, bagged sample on ice packs.

STEP 6 - Collect 3 (for a composite sample) mineral horizon samples with slide hammer corer (use bulb planter or trowel if needed), place in bag and homogenize, fill 50 ml vial.

STEP 7 – Label bag and vial: store vial on dry ice, bag on ice packs.

STEP 8 - Collect bulk density organic horizon sample (use brownie cutter), place in bag, label, and store on ice packs.

STEP 9 - Collect bulk density mineral horizon sample (only use slide hammer corer), place in bag, label and store on ice packs.

STEP 10 - Backfill boreholes in accordance with permit.

STEP 11 – Thoroughly clean equipment using deionized water.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

APPENDIX B CHECKLISTS

CHECKLIST 1: COLLECTING QUALITY SOIL SAMPLES FOR BIOGEOCHEMICAL ANALYSIS

Pre-sampling: Be sure to...

- Cold soak coolers for shipping “field-moist” samples (if required).
- Upload GPS coordinates for sample locations and review job ticket.
- Know any special permit requirements for target site.

At soil sample location: Check...

- Is designated sampling area disturbed?
- If location moved more than 1 m, did you record reasons and new (X,Y) coordinates on Data Sheet?
- Did you record metadata on Data Sheet (i.e., plot ID, date, etc...)?

Coring: Remember to...

- Change gloves between pre-determined sample locations.
- Measure soil temperature at each sample location.
- Measure and remove leaf litter before coring.
- Homogenize samples for microbial and chemical analyses.
- Core to 30 cm and measure core depth in borehole (not the corer).
- Backfill hole with appropriate material when you are done.
- Decontaminate equipment between sample locations. (e.g., slide hammer corer, tray, brownie cutter, etc...)

Sample Handling: Be sure to...

- Label sample bags.
- Store microbial samples in cooler with dry ice.
- Store chemi/phys samples in cooler with ice packs.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

Processing: At end of day...

- Transfer microbial samples to ultralow freezer in lab.
- Transfer chemical/physical samples to refrigerator.
- Use different glove for each sample.
- Homogenize, sieve, dry, and store soil as required.

CHECKLIST 2: PROCESSING SOIL SAMPLES IN THE LAB

Microbial Samples: Be sure to...

- Store in ultralow freezer (-80° C).
- Ship samples as soon as possible (within 3 days) to external lab via FedEx, priority overnight.
- Inform external lab and NEON HQ about Friday shipments/Saturday deliveries.

Bulk Density Samples: Remember to...

- Sieve, dry, and weigh the ENTIRE soil sample.

Preserve Sample Integrity: Make sure...

- Samples are sieved the same day they are collected.
- All sample label information is correctly transcribed.
- Gloves are changed and sieves cleaned between samples.
- Air- and oven-drying times are tracked appropriate datasheets.
- pH electrodes are cleaned between samples.

*Avoid cross contamination.
Be sure to change gloves between samples.*

Data Entry: Did you...

- Record the date and time of specimen processing?
- Describe irregularities or deviations from protocol?

Enter all information from data sheets into computer?

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

APPENDIX C PROTOCOL CHANGE SUMMARY

The following changes to SOPs have been made between Rev B and Rev C protocols:


- SOP B: Measure soil temperature at each soil sample location.
- SOP B: Collect soil cores for a composite sample within 0.5 m of one another, not 1 m of one another.
- SOP B: Homogenize composite sample (3 cores) in one bag and then put microbial sample into a 50 ml vial, not a bag. This applies to organic and mineral horizon samples. You no longer need to divide and homogenize organic horizon samples on trays.
- SOP B: Metadata fields for labeling sample bags and vials during soil collection are specified clearly.
- SOP B: Must use slide hammer corer for bulk density samples. You can use an alternate device that is better for the specific field site (and capable of coring down to 30 cm), such as a bulb planter, for all other soil samples. If you choose to use a device other than the slide hammer corer or the bulb planter, please notify the NEON Staff Scientist POC's via JIRA.
- SOP C: Added a procedure for analyzing field moisture of soil samples upon return to the lab.
- SOP C: Do not sieve organic horizon samples for nutrient and isotope analysis, pH analysis, or archiving. You will still sieve mineral horizon samples.
- SOP C: Subsamples for nutrient and isotopic analysis are oven-dried at 60 deg C for 48 h instead of air-dried. They are oven-dried in open 18 ml scintillation vials that are capped and shipped upon conclusion of oven-drying. You will still air-dry the rest of the soil sample for pH analyses and archiving.
- SOP C: Subsamples that are being air-dried for pH and archiving can be left in open paper lunch bags and the bags do not have to be rolled down (please do not rip and roll down bags).
- SOP C: Analyze pH of soil samples in calcium chloride (one analysis) and deionized water (second, additional analysis). Both results are recorded and reported.
- SOP C: Bulk density organic horizon samples should not be sieved.
- SOP D: For shipping soils, include a copy of receiving lab's soil permit, affix permit and required PPQ stickers to outside of box, and comply with all other requirements of the receiving lab.

Title: TOS Protocol and Procedure: Soil Physical, Chemical, and Microbial Measurements		Date: 09/15/2014
NEON Doc. #: NEON.DOC.014048	Author: E. Hinckley	Revision: D

APPENDIX D SAMPLE SHIPPING INFORMATION

The following provides information regarding shipping of samples:

- Check USDA list of soil quarantine. If your site/domain fall within any of these quarantined areas, soil shipments must include NEON’s USDA quarantine soil permit. Quarantined areas can be found at: <[7 CFR Part 301 Domestic Quarantine Notices of the Plant Protection Act \(7 U.S.C. 7756\)](#)>. Quarantine areas can change, so be sure sites/domains are up to date with shipping requirements.
- Microbe samples must be shipped on dry ice. In order to comply with US Department of Transportation and International Air Transport Association regulations, the following information is required on the dry ice label (below) on the package: weight in kg of dry ice, domain office address (shippers name and address) and contract laboratory address.

shippers declaration not required	airwaybills/airbills must have the following:
part B is required	1. "Dangerous Goods - shippers declaration not required"
dry ice amount must be in kilograms	2. Dry Ice;9 UN1845
note 2 lbs = 1 kg	3. $\frac{\text{Number}}{\text{pkgs}} \times \frac{\text{wt}}{\text{kg}}$
	
DRY ICE, _____kg	UN1845
shippers name and address _____ _____ _____	consignee name and address _____ _____ _____
9	